

---

# **pyg4ometry Documentation**

***Release 1.0.0***

**Royal Holloway**

**Jul 08, 2021**



# CONTENTS

<b>1</b>	<b>Licence &amp; Disclaimer</b>	<b>3</b>
<b>2</b>	<b>Authorship</b>	<b>5</b>
<b>3</b>	<b>Installation</b>	<b>7</b>
3.1	Requirements . . . . .	7
3.2	Installation . . . . .	7
3.3	Docker image . . . . .	8
3.4	Linux installation . . . . .	8
3.5	FreeCAD support for CAD to GDML conversion . . . . .	8
3.6	Python 3.9 . . . . .	9
<b>4</b>	<b>Introduction</b>	<b>11</b>
4.1	Need for programatic geometry generation . . . . .	11
4.2	Geant4 key concepts . . . . .	11
4.3	Geometry key concepts . . . . .	11
4.4	Implementation concepts . . . . .	11
4.5	Publications . . . . .	12
<b>5</b>	<b>Basic python geometry scripting</b>	<b>13</b>
5.1	Precepts . . . . .	13
5.2	Units . . . . .	13
5.3	Geant4 Python Scripting . . . . .	14
5.4	GDML Defines . . . . .	14
5.5	Solids . . . . .	16
5.6	Materials . . . . .	16
5.6.1	NIST Materials . . . . .	17
5.7	Detector Construction . . . . .	18
5.8	Transformations & Physical Volumes . . . . .	18
5.9	Optical Surfaces . . . . .	19
5.10	Registry and GDML Output . . . . .	19
5.11	Visualisation . . . . .	19
5.12	Overlap Checking . . . . .	19
5.12.1	Colour Coding . . . . .	20
5.12.2	Limitations . . . . .	21
5.12.3	Assemblies . . . . .	21
5.13	GDML Output . . . . .	21
<b>6</b>	<b>Tutorials</b>	<b>23</b>
6.1	GDML Loading . . . . .	23
6.2	STL Loading . . . . .	23
6.3	STEP/STP Loading . . . . .	24
6.4	Merging Geometry . . . . .	24
6.5	Assembly Conversion . . . . .	26
6.6	STL Output . . . . .	26

6.7	GDML Conversion to FLUKA . . . . .	26
6.8	Conversion of FLUKA To GDML . . . . .	27
6.9	Geometry Complexity Analysis . . . . .	29
<b>7</b>	<b>Advanced tutorials</b>	<b>33</b>
7.1	Finding volumes . . . . .	33
7.2	Navigating the LV-PV hierarchy . . . . .	33
7.3	Edit existing geometry . . . . .	33
7.4	Complex geometry builder . . . . .	34
7.5	Fluka geometry scripting . . . . .	34
7.6	Export scene to paraview/vtk . . . . .	34
7.7	Export scene to unity/unreal . . . . .	34
<b>8</b>	<b>Module Contents</b>	<b>37</b>
8.1	Defines and variables . . . . .	37
8.2	Geant4 solids . . . . .	41
8.3	Geant4 module . . . . .	53
8.4	VTK module . . . . .	58
8.5	Freecad module . . . . .	60
8.6	STL module . . . . .	61
8.7	GDML module . . . . .	61
8.8	Fluka bodies . . . . .	64
8.9	Fluka module . . . . .	72
8.10	Transformation . . . . .	72
<b>9</b>	<b>Developer</b>	<b>75</b>
9.1	Unit tests . . . . .	75
9.2	Coverage . . . . .	75
9.3	Profiling . . . . .	75
9.4	Updating A Version . . . . .	75
9.5	Updating Copyright . . . . .	75
<b>10</b>	<b>Version History</b>	<b>77</b>
10.1	v 1.0.0 - 2021 / 07 / 01 . . . . .	77
10.2	Pre-History . . . . .	77
<b>11</b>	<b>Indices and tables</b>	<b>79</b>
	<b>Python Module Index</b>	<b>81</b>
	<b>Index</b>	<b>83</b>

pyg4ometry is a package to create, load, write and visualise solid geometry for particle tracking simulations.



## LICENCE & DISCLAIMER

pyg4ometry Copyright (C) Royal Holloway, University of London 2015 - 2021.

This file is part of pyg4ometry.

pyg4ometry is free software: you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation version 3 of the License.

pyg4ometry is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with pyg4ometry. If not, see <<http://www.gnu.org/licenses/>>.





**AUTHORSHIP**

The following people have contributed to pyg4ometry:

- Stewart Boogert (RHUL)
- Andrey Abramov (RHUL -> CERN)
- Alistair Butcher (RHUL -> Amazon)
- Cedric Hernalsteens (ULB -> CERN)
- Laurie Nevay (RHUL)
- William Shields (RHUL)
- Ben Shellswell (former RHUL)
- Elliott Ramoisiaux (ULB)
- Stuart Walker (RHUL -> DESY)



## INSTALLATION

### 3.1 Requirements

- pyg4ometry is developed exclusively for Python 3 (Python2 is deprecated) - recommend up to Python 3.8 currently as no VTK wheels for 3.9.
- VTK (Visualisation toolkit)
- Freecad
- antlr4
- cython
- GitPython
- matplotlib
- CGAL
- pybind11

### 3.2 Installation

To install pyg4ometry, simply run `make install` from the root pyg4ometry directory:

```
cd /my/path/to/repositories/  
git clone http://bitbucket.org/jairhul/pyg4ometry  
git checkout develop  
cd pyg4ometry  
  
make install
```

---

**Note:** To build using the git directory and not installing into `/usr/local` use `make develop` instead of `make install`

---

To build pycsg with cpython:

```
make build_ext
```

Or install from pypi:

```
pip install pyg4ometry
```

or alternatively, run `make develop` from the same directory to ensure that any local changes are picked up.

### 3.3 Docker image

1. Download and install [Docker desktop](#)
2. open a terminal (linux) or cmd (windows)
3. (windows) Start [Xming](#) or [Vxsr](#)
4. Download the [pyg4ometry docker file](#)
5. `docker build -t ubuntu-pyg4ometry -f Dockerfile-ubuntu-pyg4ometry .`

If you need to update increment the variable ARG PYG4OMETRY\_VER=1

To start the container

1. open a terminal (linux/mac) or cmd (windows)
2. get your IP address `ifconfig` (linux/mac) or `ipconfig /all` (windows)
3. Start XQuartz (mac) or Xming/Vxsr (windows). For Xming/Vxsr (might need to play with the settings when launching)
4. `docker run -ti -v /tmp/.X11-unix:/tmp/.X11-unix -v YOURWORKDIR:/tmp/Physics -e DISPLAY=YOUR_IP ubuntu-pyg4ometry (the -v /tmp/.X11-unix:/tmp/.X11-unix is only required for mac/linux)`

Test the installation

1. `docker> cd pyg4ometry/pyg4ometry/test/pythonGeant4/`
2. `docker> ipython`
3. `python> import pyg4ometry`
4. `python> import T001_Box`
5. `python> T001_Box.Test (True, True)`

### 3.4 Linux installation

There are docker files for Centos 7 and Ubuntu 20. The docker files can be used as list of instructions for installation for each of these OSes.

- [Ubuntu 20.02](#)
- [Centos 7](#)

### 3.5 FreeCAD support for CAD to GDML conversion

For FreeCAD support and you already have it installed you need to add library to PYTHONPATH, for example

```
export PYTHONPATH=/opt/local/libexec/freecad/lib/
```

Building FreeCAD can be a pain for MAC so

```
mkdir FreeCAD
cd FreeCAD
set FCROOT=$pwd
wget https://github.com/FreeCAD/FreeCAD/archive/0.19_pre.tar.gz
tar xzf 0.19_pre.tar.gz
mkdir build
mkdir install
cd build
cmake ../FreeCAD-0.18.4 -DCMAKE_INSTALL_PREFIX=../install \
-DCOIN3D_LIBRARIES=/opt/local/Library/Frameworks/Inventor.framework/Libraries/
↪ libCoin.dylib -DBUILD_FEM=0 \
```

(continues on next page)

(continued from previous page)

```
-DBUILD_MATERIAL=0 -DBUILD_SHIP=0 -DBUILD_DRAFT=0 -DBUILD_TUX=0 -DBUILD_ARCH=0 -  
↪DBUILD_PLOT=0 \  
-DBUILD_OPENSCAD=0  
make -jN  
make install  
export PYTHONPATH=$PYTHONPATH:$FCROOT/install
```

## 3.6 Python 3.9

Generally we recommend up to Python 3.8.

At the time of writing, there are no VTK distributions for Python 3.9 on pypi. However, you can have VTK with Python 3.9 through say MacPorts or by compiling it yourself. In this case, you can comment out the VTK requirement from the setup.py around line 86.

Similarly, there are fixed version requirements for networkx and antlr. These specific versions will not be available for Python 3.9 but newer versions will likely work. In this case, you can remove the fixed version requirement (leaving only the name).

**Warning:** ANTLR will create an unbelievable amount of warnings when using a different ANRLR version that the one the parser was generated with. It should work though.



## INTRODUCTION

This package started as an internal tool for the BDSIM and machine backgrounds group at Royal Holloway. BDSIM is a tool to rapidly create Geant4 models of accelerator systems. Creation of geometry is a time consuming activity and pyg4ometry hopefully will improve the time taken to create accurate reliable geometry files.

### 4.1 Need for programatic geometry generation

- Non-expert user creation and maintenance of geometry
- Reduce time spent creating geometry
- Reproducibility
- Lower number of errors
- Parameterisation of geometry
- Visualisation of geometry
- Overlap checking
- Import from other geometry packages

### 4.2 Geant4 key concepts

- GMDL

### 4.3 Geometry key concepts

- Constructive Solid Geometry (CSG)
- Boolean operations
- Boundary representation (B-REP)
- Boundary mesh

### 4.4 Implementation concepts

- Registry
- Parameter
- ParameterVector
- Pycsg

## 4.5 Publications

### On pyg4ometry

- Pyg4ometry : A Tool To Create Geometries For Geant4, Bdsmi, G4Beamline and Fluka For Particle Loss and Energy Deposit Studies, IPAC2019, Melbourne, Australia, 2019 [Google scholar cites](#)



## BASIC PYTHON GEOMETRY SCRIPTING

### 5.1 Precepts

- Units may be specified but default to Geant4 ones (e.g. mm, rad).
- Rotations are made using Tait-Bryan angles (rotation about reference x,y,z axes).
- A `Registry` object should be used to hold all things related in a model and passed into the constructors of most objects.
- GDML-like **full lengths** are used instead of typically half lengths

### 5.2 Units

- The default units are mm and rad for length and angle.
- Most constructors will take units as an optional key word argument ('kwarg').
- The kwargs are typically `lunit` for length unit and `angle` for angle unit.
- Units are defined in `pyg4ometry.gdml.Units.py`.

The following units (as strings) are accepted:

Unit	Value
nm	1e-6
um	1e-3
mm	1
cm	10
m	1e3
km	1e6
deg	$\pi/180$
degree	$\pi/180$
rad	1
radian	1
mrاد	1e-3
urad	1e-6
eV	1e-3
none	1

Examples:

```
reg = pyg4ometry.geant4.Registry()
boxSolid = pyg4ometry.geant4.solid.Box("aBox", 10, 20, 30, reg)
```

This defines a box with the default units (none specified), so mm. We can specify them:

```
boxSolid = pyg4ometry.geant4.solid.Box("aBox", 10, 20, 30, reg, "cm")
```

## 5.3 Geant4 Python Scripting

Making use of pyg4ometry requires the following modules

```
import pyg4ometry
```

To make a simple geometry of a box located at the origin

```
1 # load pyg4ometry
2 import pyg4ometry
3
4 # registry to store gdml data
5 reg = pyg4ometry.geant4.Registry()
6
7 # world solid and logical
8 ws = pyg4ometry.geant4.solid.Box("ws", 50, 50, 50, reg)
9 wl = pyg4ometry.geant4.LogicalVolume(ws, "G4_Galactic", "wl", reg)
10 reg.setWorld(wl.name)
11
12 # box placed at origin
13 b1 = pyg4ometry.geant4.solid.Box("b1", 10, 10, 10, reg)
14 b1_l = pyg4ometry.geant4.LogicalVolume(b1, "G4_Fe", "b1_l", reg)
15 b1_p = pyg4ometry.geant4.PhysicalVolume([0, 0, 0], [0, 0, 0], b1_l, "b1_p", wl, reg)
16
17 # visualise geometry
18 v = pyg4ometry.visualisation.VtkViewer()
19 v.addLogicalVolume(wl)
20 v.addAxes(20)
21 v.view()
```

Here is the vtk visualiser output of the above example

## 5.4 GDML Defines

In GDML there are multiple `define` objects that can be used parameterise geometry, materials etc. These can be used as variables or definitions and mean that any equations used will be retained in GDML output. For example a GDML constant can be created in the following way

```
# registry to store gdml data
reg = pyg4ometry.geant4.Registry()

# constant called x
x = pyg4ometry.gdml.Constant("x", 10, reg)
```


The normal set of mathematical operations in python can be performed and evaluated

```
y = 2*x + 10
y.eval()
```

```
>> 30
```

The constant `x` can of course be changed and `y` re-evaluated

```
x.setExpression(5)
y.eval()
```



```
>> 20
```

**Note:** Standard mathematical functions can be used with GDML defines (Constant, Variable, etc). So sin, cos, tan, exp and so on, but pyg4ometry functions have to be used

```
1 x = pyg4ometry.gdml.Constant("x",10,reg)
2 cx = pyg4ometry.gdml.cos(x)
```

So the box example above can be rewritten using constants

```
1 # load pyg4ometry
2 import pyg4ometry
3
4 # registry to store gdml data
5 reg = pyg4ometry.geant4.Registry()
6
7 bx = pyg4ometry.gdml.Constant("bx","10",reg,True)
8 by = pyg4ometry.gdml.Constant("by",2*bx,reg,True)
9 bz = pyg4ometry.gdml.Constant("bz",2*by,reg,True)
10
11 # world solid and logical
12 ws = pyg4ometry.geant4.solid.Box("ws",50,50,50,reg)
13 wl = pyg4ometry.geant4.LogicalVolume(ws,"G4_Galactic","wl",reg)
14
15 # box placed at origin
16 b1 = pyg4ometry.geant4.solid.Box("b1",bx,by,bz,reg)
17 b1_l = pyg4ometry.geant4.LogicalVolume(b1,"G4_Fe","b1_l",reg)
```

(continues on next page)

(continued from previous page)

```

18 b1_p = pyg4ometry.geant4.PhysicalVolume([0,0,0],[0,0,0],b1_l,"b1_p",wl,reg)
19
20 # visualise geometry
21 v = pyg4ometry.visualisation.VtkViewer()
22 v.addLogicalVolume(wl)
23 v.addAxes(20)
24 v.view()

```

**Note:** All GDML defines (Constant, Variable, etc) can be used in the construction of other pyg4ometry classes interchangeably instead of floats or strings (where strings are either numbers or a GDML expression)

**Warning:** Avoid reassigning variables used as defines, this can have unexpected consequences so for example

```

1 b1 = pyg4ometry.geant4.solid.Box("b1",bx,by,bz,reg)
2 b1.pX = 20 # do not do this
3 b1.pX.setExpression(20) # rather do this

```

## 5.5 Solids

The python geant4 solids match the Geant4 constructors as much possible (different constructor signatures are not supported in python). For example looking at the G4Box class

```
pyg4ometry.geant4.solid.Box(name, pX, pY, pZ, registry, lunit)
```

```
G4Box(const G4String& pName, G4double pX, G4double pY, G4double pZ)
```

A full list of solids can be found in *Geant4 solids*.

**Warning:** The parameters stick to the GDML convention of **full** lengths opposed to half lengths.

## 5.6 Materials

As with solids materials are defined in a similar way to Geant4 C++. Python does not have overloaded constructors, so unique signatures are needed, in contrast to Geant4.

To define a material from the Geant4 predefined (e.g. NIST) materials

```

1 import pyg4ometry.geant4 as _g4
2 wm = _g4.MaterialPredefined("G4_Galactic")
3 bm = _g4.MaterialPredefined("G4_Fe")

```

To define a single element in terms of atomic number, atomic mass and density.

```

1 import pyg4ometry.geant4 as _g4
2 wm = _g4.MaterialSingleElement("galactic",1,1.008,1e-25,reg) # low density_
  ↪hydrogen
3 bm = _g4.MaterialSingleElement("iron",26,55.8452,7.874,reg) # iron at near room_
  ↪temp

```

To define a compound two elements using the mass fraction

```

1 import pyg4ometry.geant4 as _g4
2 wm = _g4.MaterialCompound("air", 1.290e-3, 2, reg)
3 ne = _g4.ElementSimple("nitrogen", "N", 7, 14.01)
4 oe = _g4.ElementSimple("oxygen", "O", 8, 16.0)
5 wm.add_element_massfraction(ne, 0.7)
6 wm.add_element_massfraction(oe, 0.3)
7 bm = _g4.MaterialSingleElement("iron", 26, 55.8452, 7.874, reg)      # iron at near room_
↪temp

```

To define a compound using number of atoms

```

1 import pyg4ometry.geant4 as _g4
2 bm = _g4.MaterialCompound("plastic", 1.38, 3, reg)      # Generic PET C_10 H_8 O_4
3 he = _g4.ElementSimple("hydrogen", "H", 1, 1.008)
4 ce = _g4.ElementSimple("carbon", "C", 6, 12.0096)
5 oe = _g4.ElementSimple("oxygen", "O", 8, 16.0)
6 bm.add_element_natoms(he, 8)
7 bm.add_element_natoms(ce, 10)
8 bm.add_element_natoms(oe, 4)

```

Material as a mixture of materials

```

1 import pyg4ometry.geant4 as _g4
2 bm = _g4.MaterialCompound("YellowBrass_C26800", 8.14, 2, reg)
3 copper = _g4.MaterialPredefined("G4_Cu")
4 zinc = _g4.MaterialPredefined("G4_Zn")
5 bm.add_material(copper, 0.67)
6 bm.add_material(zinc, 0.33)

```

Example of elements formed by isotopes

```

1 import pyg4ometry.geant4 as _g4
2 u235 = _g4.Isotope("U235", 92, 235, 235.044)
3 u238 = _g4.Isotope("U238", 92, 238, 238.051)
4 uranium = _g4.ElementIsotopeMixture("uranium", "U", 2)
5 uranium.add_isotope(u235, 0.00716)
6 uranium.add_isotope(u238, 0.99284)
7 bm = _g4.MaterialCompound("natural_uranium", 19.1, 1, reg)
8 bm.add_element_massfraction(uranium, 1)

```

## 5.6.1 NIST Materials

Geant4 has many predefined materials according to the NIST database. Their name typically starts with G4\_. These typically can be used with MaterialPredefined and we **do not need** to specify the full composition - Geant4 will find them at run time.

However, in the case of conversion to FLUKA, these are fully expanded according to their definition in Geant4 based on a cache in pyg4ometry of the material compositions generated using BDSIM from Geant4 (10.7.p01 as of writing). Should the user wish to use these, they can be accessed from the functions in the geant4 module.

```

1 import pyg4ometry
2 nistHydrogenElement = pyg4ometry.geant4.nist_element_2geant4Element('G4_H')

```

Note, an ‘element’ cannot be used as a ‘material’ in a logical volume. We must upgrade it to a material for that. The NIST elements contain the appropriate mixture of natural isotopes and can be used in MaterialCompound as demonstrated above.

Alternatively, we can access the NIST materials and materials of elements.

```

1 import pyg4ometry
2 nistHydrogenMaterial = pyg4ometry.geant4.nist_material_2geant4Material('G4_H')
3 nistConcreteMaterial = pyg4ometry.geant4.nist_material_2geant4Material('G4_CONCRETE
↪')

```

(continues on next page)

## 5.7 Detector Construction

This largely proceeds in exactly the same way as in G4 or GDML. Hierarchy of solids, booleans, logical, physical (replica, division, param) volumes.

0. Create registry to hold everything
1. Create solids
2. Create logical volumes
3. Place logical volumes (construct physical volumes)
4. Visualise
5. Check
6. Export

## 5.8 Transformations & Physical Volumes

Transformations in 3D are essential for the easy placement of solids in a CSG tree or LV placement. There is not a specific transformation class like in Geant4. The matrices and vectors used for placements are here typically Numpy arrays or matrices.

Geant4 has two possible constructors for a physical volume. These provide active and passive transformations. In pyg4ometry, only one is provided.

- The transform in a physical volume first translates the placed logical volume with respect to the mother logical, then rotates it.

The physical volume class is documented here: [Geant4 module](#), but an example is shown here.

```
1 import pyg4ometry
2 r = pyg4ometry.geant4.Registry()
3 vacuum = _g4.MaterialPredefined("G4_Galactic")
4 water = _g4.MaterialPredefined("G4_WATER")
5 worldSolid = pyg4ometry.geant4.solid.Box("world_solid", 100, 100, 100, reg)
6 boxSolid = pyg4ometry.geant4.solid.Box("box_solid", 10, 20, 40, reg)
7 worldLV = pyg4ometry.geant4.LogicalVolume(worldSolid, vacuum, "world_lv", reg)
8 boxLV = pyg4ometry.geant4.LogicalVolume(boxSolid, water, "box_lv", reg)
9
10 pyg4ometry.geant4.PhysicalVolume([0,0,0],
11                                  [0,0,0],
12                                  boxLV,
13                                  "box_pv",
14                                  worldLV,
15                                  reg)
```

This creates a box of water inside a box of vacuum. The box of water is 10 x 20 x 50 mm long (note mm are the default length units), and it is placed with no offset and no rotation (i.e. at the centre) of the world volume. Alternatively:

```
1 import numpy as np
2 pyg4ometry.geant4.PhysicalVolume([0,np.pi/3.0,0],
3                                   [0,0,0],
4                                   boxLV,
5                                   "box_pv",
6                                   worldLV,
7                                   reg)
```

In this case, the box is placed with no offset but with a rotation of  $\pi/3$  radians about the y axis of the world box.

**Note:** The rotations are Tait-Bryan angles, which are rotations about the reference x,y,z axes. i.e. if there is a rotation about both x and y, these are independent and it is **not** a compound frame that is rotated. These are commonly thought of like an aircraft and called pitch, yaw and tilt.

There are utility functions for translation between different transformations in `pyg4ometry.transformation`. See [Transformation](#).

## 5.9 Optical Surfaces

## 5.10 Registry and GDML Output

Strictly speaking a registry class to store all of the GDML is not required. As with normal Geant4 given a `lv` pointer it should be possible to form an aggregation hierarchy that contains all necessary objects. Now GDML breaks this as the structure is built up using `name` tags. For example a placement requires a position. In Geant4 this would just be a pointer to an transformation object, but GDML has two mechanisms to represent this, firstly child nodes of a `PhysicalVolume` tag or secondly a position define, see below

The registry class is a storage class for a complete GDML file. At the construction stage of almost all objects a registry is required. If the object is added to the registry then it will appear explicitly in the GDML output

## 5.11 Visualisation

Any logical volume `lv` can be visualised using:

```
1 v = pyg4ometry.visualisation.VtkViewer()
2 v.addLogicalVolume(lv)
3 v.addAxes(20)
4 v.view()
```

which will open a Vtk render window. The render window now receives keyboard and mouse commands. To exit render window `q`, to restart interaction with the visualiser

```
1 v.start()
```

There are also convenience methods of `pyg4ometry.visualisation.VtkViewer()` that allow changing of the viewing parameters. So if the viewer is active then render window needs to be stopped `q` and then commands can be typed into the terminal, for example

```
1 v.setOpacity(0.1)
2 v.setWireframe()
3 v.start()
```

## 5.12 Overlap Checking

“Overlaps” is a general term used to describe malformed geometry. Such geometry is unphysical and may cause particle tracking problems in simulations such as stuck particles, or particles completely missing certain volumes entirely. Such errors are rarely easy to spot from results or running the simulation.

Given all the PVs (daughters) of a LV (mother) should be bounded by the LV/mother solid. It is possible to check between all daughter solid meshes and between daughters and the mother solid mesh. Given an `pyg4ometry.geant4.LogicalVolume` instance (“lv”), this check can be performed by calling the following code:


```
lv.checkOverlaps()
```

This will check only the immediate daughters of this logical volume. To descend further into a geometry, the recursive flag can be used:

```
lv.checkOverlaps(recursive=True)
```

See *Geant4 module*: `LogicalVolume.checkOverlaps()` for full details. A more complete example is:

```
1 # cd pyg4ometry/pyg4ometry/test/pythonGeant4
2 import pyg4ometry
3 r = pyg4ometry.freecad.Reader("./T103_overlap_cop1.gdml")
4 l = r.getRegistry().getWorldVolume()
5 l.checkOverlaps(recursive=False, coplanar=True, debugIO=False)
6 v = pyg4ometry.visualisation.VtkViewer()
7 v.addLogicalVolume(l)
8 v.view()
```



Text is by default only printed out when an overlap is found. Any overlaps will be prepared for visualisation in a VtkViewer (must be constructed and given the LV after this).

The following overlap checks are performed:

1. daughter with other daughter overlap
2. co-planar daughter with other daughter overlap
3. protrusion of a daughter from the mother volume
4. co-planar daughter with mother volume

### 5.12.1 Colour Coding

In the visualiser, text will be overlaid saying “overlap” where some kind of overlap is detected. Additionally, the actual overlap itself will be visualised and colour coded according to:



- red: protrusion overlap
- green: daughter-daughter overlap
- blue: co-planar overlap

### 5.12.2 Limitations

1. The overlap detection is performed by checking for overlaps in the visualisation meshes generated for each volume. In the case of curved solids (e.g. a cylinder), the mesh is not truly curved but a polygon. Very closely spaced curved surfaces may produce false overlaps. By default, all curved solids will use the same number of points around a circle, so usually we can “get away” with this if the curved solids aren’t rotated about their axis.
2. Currently, division and parameterised volumes are not handled explicitly.

### 5.12.3 Assemblies

In the case of assembly volumes, and if an overlap is detected, a unique name is built up based on the parent `PhysicalVolume`, the assembly and the `PhysicalVolume` inside it. Furthermore, this is done recursively if assemblies of assemblies (etc) are used. The name is built up with an underscore “\_” for padding and the user should decode this from their input.

As there is no ‘mother’ of an assembly, there is no mother protrusion directly. The contents of an assembly are compared to all other daughters and the mother at the higher level in which they are placed.

## 5.13 GDML Output

To write an GDML file given a `pyg4ometry.geant4.registry` instance `reg`.

```
1 import pyg4ometry
2 w = pyg4ometry.gdml.Writer()
3 w.addDetector(reg)
4 w.write('file.gdml')
5 # make a quick bdsim job for the one component in a beam line
6 w.writeGmadTester('file.gmad', 'file.gdml')
```




## TUTORIALS

### 6.1 GDML Loading

In directory `pyg4ometry/pyg4ometry/test/gdmlG4examples/ChargeExchangeMC/`


```
1 import pyg4ometry
2 r = pyg4ometry.gdml.Reader("lht.gdml")
3 l = r.getRegistry().getWorldVolume()
4 v = pyg4ometry.visualisation.VtkViewer()
5 v.addLogicalVolume(l)
6 v.view()
```



### 6.2 STL Loading

STL files are typically used for a single watertight solid mesh. This mesh is converted to a `TessellatedSolid` and then a logical volume which can be placed in a geometry. In directory `pyg4ometry/pyg4ometry/test/stl`.

```
import pyg4ometry
reg = pyg4ometry.geant4.Registry()
r = pyg4ometry.stl.Reader("utahteapot.stl")
l = r.logicalVolume("test", "G4_Cu", reg)
v = pyg4ometry.visualisation.VtkViewer()
v.addLogicalVolume(l)
v.view()
```




## 6.3 STEP/STP Loading

In directory `pyg4ometry/pyg4ometry/test/freecad`

```
1 import pyg4ometry
2 r = pyg4ometry.freecad.Reader("./08_AshTray.step")
3 r.relabelModel()
4 r.convertFlat()
5 l = r.getRegistry().getWorldVolume()
6 v = pyg4ometry.visualisation.VtkViewer()
7 v.addLogicalVolume(l)
8 v.view()
```

## 6.4 Merging Geometry

There are ways to incorporate geometry from multiple sources in GDML. This has potentially lots of problems as each file needs to be a well formed GDML file and care has to be taken with degenerate names from the different sources. For example a volume can be extracted from `GdmlFile1` and added to `GdmlFile2`, clearly all solids, materials and variables need to also be transferred. For this example we need two GDML files, so `pyg4ometry/`



test/pythonGeant4/T001\_Box.py and pyg4ometry/test/pythonGeant4/T002\_Tubs.py, so run them

```
1 import T001_Box
2 T001_Box.Test(True, True)
3
4 import T002_Tubs
5 T002_Tubs(True, True)
```

This will create two GDML files T001\_Box.gdml and T002\_Tubs.gdml. It is possible to find the volumes contained in each file (using the tubs gdml file as the example) by performing the following

```
1 import pyg4ometry
2 r = pyg4ometry.gdml.Reader("T002_Tubs.gdml")
3 reg = r.getRegistry()
4
5 # printing the names of the logical volumes
6 print(reg.logicalVolumeDict.keys())
7
8 # printing the names of the physical volumes
9 print(reg.physicalVolumeDict.keys())
10
11 lv = reg.logicalVolume["t1"]
```

Now merging the t1 logicalVolume (which is a simple tubs) with the box gdml file

```
1 import pyg4ometry
2 r1 = pyg4ometry.gdml.Reader("T001_Box.gdml")
3 reg1 = r1.getRegistry()
4
```

(continues on next page)

(continued from previous page)

```

5 r2 = pyg4ometry.gdml.Reader("T002_Tubs.gdml")
6 reg2 = r2.getRegistry()
7
8 lv = reg2.logicalVolumeDict["t1"]
9
10 # create physical volume with placement
11 pv = pyg4ometry.geant4.PhysicalVolume([0,0,0],[50,0,0], lv, "t1_pv", reg1.
    ↪getWorldVolume(), reg1)
12
13 reg1.addVolumeRecursive(pv)
14
15 # gdml output
16 w = pyg4ometry.gdml.Writer()
17 w.addDetector(reg1)
18 w.write("MergeRegistry.gdml")

```

**Note:** In the example two registry objects are created and objects from reg2 are merged into reg1. Of course one registry might be formed by pyg4ometry commands opposed created from a file.

**Warning:** The pv needs to added with addVolumeRecursive otherwise it is possible that GDML definitions which lv depends on are not transferred over.

## 6.5 Assembly Conversion

Given two sources of geometry, placement of top level world logical volume solids will likely result in an overlap. To avoid these types of problems, it might required to convert one of the logical volumes to an AssemblyVolume.

## 6.6 STL Output

To write an STL file from `m = volume.pycsgmesh()`

```

1 vtkConverter = vtk.Convert()
2 vtkPD        = vtkConverter.MeshListToPolyData(m)
3 r = vtk.WriteSTL("file.stl", vtkPD)

```

## 6.7 GDML Conversion to FLUKA

It is possible convert a pyg4ometry geometry to FLUKA. This is currently a work in progress and not all Geant4-GDML constructions are implemented, although they can be quickly added. Given a LV variable named `logical`

```

1 import pyg4ometry
2 reader = pyg4ometry.gdml.Reader("input.gdml")
3 logical = reader.getRegistry().getWorldVolume()
4 freg = pyg4ometry.convert.geant4Logical2Fluka(logical)
5 w = pyg4ometry.fluka.Writer()
6 w.addDetector(freg)
7 w.write("FileName.inp")

```


If you want to load a file into Flair then a flair file can be written based on `FileName.inp` using the following

```

1 extent = logical.extent(includeBoundingSolid=True)
2 f = pyg4ometry.fluka.Flair("FileName.inp", extent)
3 f.write("FileName.flair")

```

Here is an example (viewed in Flair) of a simple Geant G4 solid that has been converted to FLUKA using this method



**Note:** All GDML placements are respected in the conversion from GDML to FLUKA, for both Placements and Boolean Solids. So for example a tree of LV-PV placements are reduced into a single transformation of a LV into a global coordinate space for FLUKA. A similar process is used for a tree of CSG operations.


**Warning:** Currently there are some things which are not implemented in the conversion. 1) Materials, 2) Scaled solids, 3) Reflections in placements, 4) Division, replica and parameterised placements. Some of these are straight forward to implement, like Materials and the non-Placement physical volumes can be done quickly if a user requires it.

## 6.8 Conversion of FLUKA To GDML

FLUKA geometry can be converted to GDML using `pyg4ometry.convert.fluka2geant4`. The conversion process is robust and supports all FLUKA geometry constructs. Given a FLUKA file *model.inp*, the following code can be used to translate it to a GDML file.

```
1 import pyg4ometry.fluka as fluka
2 import pyg4ometry.gdml as gdml
3 from pyg4ometry.convert import fluka2Geant4
4
5 # Read the FLUKA file, get the FlukaRegistry, convert the registry to a
```

(continues on next page)



(continued from previous page)

```

6 # Geant4 Registry
7 reader = fluka.Reader("model.inp")
8 flukaregistry = reader.flukaregistry
9 geant4Registry = fluka2Geant4(flukaRegistry)
10
11 worldLogicalVolume = geant4Registry.getWorldVolume()
12 worldLogicalVolume.clipSolid()
13
14 writer = gdml.Writer()
15 writer.addDetector(geant4Registry)
16 writer.write("model.gdml")

```


The core of this functionality is the translation of the *FlukaRegistry* instance into the equivalent *Registry* (i.e. *Geant4*) instance.

Here is an example of a model viewed in flair and the resulting visualisation in VTK of the *Geant4* model

A number of keyword arguments are available to further modify the conversion. The *fluka2Geant4* keyword arguments *region* and *omitRegions* allow the user to select a subset of the named regions to be translated.

The conversion of QUA bodies (*fluka2geant4* kwarg *quadricRegionAABBs*) is complex and requires further explanation. In *Pyg4ometry* the mesh and GDML representations of FLUKA infinite circular cylinders, elliptical cylinders and half-spaces are all finite (but very large) cylinders, elliptical cylinders and boxes. This is robust as increasing the length of cylinders and depth/bredth of boxes does not increase the number of polygons used in the underlying mesh representation for that solid. However, this is not true of the quadric surface. A quadric surface cannot simply be generated to be “very large”, as the number of polygons will grow quickly, along with the memory consumption and facets in the resulting GDML TesselatedSolid, which will also slowing down tracking time in *Geant4*. For this reason the user must provide axis-aligned bounding boxes of the regions where any QUA bodies are present. It is recommended that these boxes be a centimetre larger than formally necessary to ensure a correct conversion. Providing the bounding box ensures that an efficient and accurate mesh of the QUA bodies can be generated meaning that the conversion to be performed in a tractable amount of time as well giving more performant tracking in *Geant4*.





## 6.9 Geometry Complexity Analysis

For a given logical volume we can get some statistics on the complexity of the geometry. A simple class called *GeometryComplexityInformation* is returned that has a series of dictionaries with information.

```
cd pyg4ometry/pyg4ometry/test/gdmlCompoundExamples/bdsim_2
ipython
>>> import pyg4ometry
>>> r = pyg4ometry.gdml.Reader("22-size-variation-facetcrop-quad.gdml")
>>> info = pyg4ometry.geant4.AnalyseGeometryComplexity(r.getRegistry().
↳getWorldVolume())
>>> info.printSummary()
Types of solids
ExtrudedSolid      : 96
Tubs               : 51
Intersection       : 24
Polyhedra          : 12
Subtraction        : 6
Box                : 1


# of daughters      count
0                   : 152
2                   : 19
4                   : 12
13                  : 6
25                  : 1

Depth of booleans   count
1                   : 30

Booleans width depth over 3
Solid name          : n Booleans

>>> info.<tab>
comp.booleanDepth    comp.nDaughtersPerLV
```

(continues on next page)



(continued from previous page)

<code>comp.booleanDepthCount</code>	<code>comp.printSummary</code>
<code>comp.nDaughters</code>	<code>comp.solids</code>



## ADVANCED TUTORIALS

### 7.1 Finding volumes

Before editing geometry it is useful to find a logical volume. The registry contains all the logical volumes using the GDML in `pyg4ometry/pyg4ometry/test/gdmlG4examples/ChargeExchangeMC/`

```
1 import pyg4ometry
2 r = pyg4ometry.gdml.Reader("lht.gdml")
3 reg = r.getRegistry()
```

The registry instance `reg` has a member variable called `logicalVolumeDict` so calling

```
reg.logicalVolumeDict.keys()
```

should print

```
In [4]: reg.logicalVolumeDict.keys()
Out[4]: odict_keys(['vMonitor', 'vMonitorBack', 'vTarget', 'vTargetInnerCover',
↳ 'vTargetColumn', 'vTargetInnerColumn',
↳ 'vTargetVacuumSpace', 'vTargetOuterCover', 'vCrystal',
↳ 'vCrystalRow', 'vCalorimeter', 'vVetoCounter',
↳ 'vOuterFerrumRing', 'vInnerFerrumRing', 'vInnerCuprumRing',
↳ 'vTargetWindow', 'vTargetWindowCap',
↳ 'vTargetWindowMylarCover', 'vTargetWindowAluminiumCover',
↳ 'vWorldVisible', 'World'])
```

then the LogicalVolume can be obtained simply from the dictionary

```
lv = reg.logicalVolumeDict['vTargetInnerColumn']
```

This `lv` can be used for manipulating geometry, passing to visualisers etc.

### 7.2 Navigating the LV-PV hierarchy

There is a hierarchy of LV-PVs to describe a GDML/Geant4 geometry. An LV in terms of geometry consists of an outer solid `lv.solid` and `lv.daughterVolumes`. `lv.solid` is one of the `pyg4ometry.geant4.solid` types which match the GDML/Geant4 solids. `lv.daughterVolumes` is a list of `pyg4ometry.geant4.PhysicalVolumes`.

The best way to explore the methods and data members of `pyg4ometry.geant4.LogicalVolume` and `pyg4ometry.geant4.PhysicalVolume` is to explore in iPython. See cute video based on the `lht.gdml` example above.

### 7.3 Edit existing geometry

After loading some geometry it is possible to modify the memory resident geometry. This could adjusting the parameter of a given solid or PV, or replacing entirely the type of solid used for an LV. To edit geometry a LV

instance is required

## 7.4 Complex geometry builder

Having access to geometry construction in python allows the rapid construction of geometry using functions which return an appropriate LV. Examples of this available in `pyg4ometry/pyg4ometry/test/pythonCompoundExamples`

## 7.5 Fluka geometry scripting

In a very similar way to geant4 geometry authoring it is possible to use pyg4ometry to create fluka output. To create a simple region consisting of a single body

```
1 import pyg4ometry.convert as convert
2 import pyg4ometry.visualisation as vi
3 from pyg4ometry.fluka import RPP, Region, Zone, FlukaRegistry
4
5 freg = FlukaRegistry()
6
7 rpp = RPP("RPP_BODY", 0, 10, 0, 10, 0, 10, flukaregistry=freg)
8 z = Zone()
9 z.addIntersection(rpp)
10 region = Region("RPP_REG", material="COPPER")
11 region.addZone(z)
12 freg.addRegion(region)
13
14 greg = convert.fluka2Geant4(freg)
15 greg.getWorldVolume().clipSolid()
16
17 v = vi.VtkViewer()
18 v.addAxes(length=20)
19 v.addLogicalVolume(greg.getWorldVolume())
20 v.view()
```

## 7.6 Export scene to paraview/vtk

```
1 import pyg4ometry
```

## 7.7 Export scene to unity/unreal

The quickest way to get geometry to Unity/Unreal is to use a standard asset format. This takes a `vtkRenderer` and creates a OBJ file. The `vtkRenderer` managed within pyg4ometry from the `VtkViewer` class, once a geometry is created (either from any source) then an OBJ file can be created. Taking the example in `pyg4ometry/pyg4ometry/test/pythonCompoundExamples/`

```
1 import pyg4ometry
2 r = pyg4ometry.gdml.Reader("./Chamber.gdml")
3 l = r.getRegistry().getWorldVolume()
4 v = pyg4ometry.visualisation.VtkViewer()
5 v.addLogicalVolume(l)
6 v.exportOBJScene("Chamber")
```

obj files are written `Chamber.obj` and `Chamber.mtl`.

For a Fluka file, first it must be converted to geant4 and then the same process should be followed.

```
1 import pyg4ometry
2 r = pyg4ometry.fluka.Reader("./Chamber.inp")
3 greg = pyg4ometry.convert.fluka2geant4(r.getRegistry())
4 l = greg.getWorldVolume()
5 v = pyg4ometry.visualisation.VtkViewer()
6 v.addLogicalVolume(l)
7 v.exportOBJScene("Chamber")
```

As the meshing might need to be changed for the visualisation application, the parameters for the meshing for each solid might need to be changed.

An obj file for an entire experiment does not help with work flows where meshes have to be UV-ed and textured. Tools like Blender and Gaffer can be used for this workload but require meshes for each object and their placement. To enable this there is a special writer

```
1 import pyg4ometry
2 r = pyg4ometry.gdml.Reader("./Chamber.gdml")
3 l = r.getRegistry().getWorldVolume()
4 w = pyg4ometry.visualisation.RenderWriter()
5 w.addLogicalVolumeRecursive(l)
6 w.write("./SphericalChamber")
```

The directory `SphericalChamber` contains all the meshes in OBJ format along with an instance file `0_instances.dat` which contains a row for each instance of a mesh.





## MODULE CONTENTS

This documentation is automatically generated by scanning all the source code. Parts may be incomplete.

### 8.1 Defines and variables

`pyg4ometry.gdml.Defines.upgradeToStringExpression` (*reg, obj*)  
Take a float, str, ScalarBase and return string expression

**Parameters**

- **reg** (*Registry*) – Registry for lookup in define dictionary
- **obj** (*str, float, ScalarBase*) – Object to upgrade

**Returns** String expression

**Return type** str

**class** `pyg4ometry.gdml.Defines.ScalarBase`

Bases: object

Base class for all scalars (Constants, Quantity, Variable and Expression)

`__add__` (*other*)

`__mul__` (*other*)

`__neg__` ()

`__rsub__` (*other*)

`__sub__` (*other*)

`setExpression` (*expr*)

`setName` (*name*)

Set name of scalar

**Parameters** **name** (*str*) – name of object

`setRegistry` (*registry*)

**class** `pyg4ometry.gdml.Defines.Constant` (*name, value, registry, addRegistry=True*)

Bases: `pyg4ometry.gdml.Defines.ScalarBase`

GDML constant define wrapper object

**Parameters**

- **name** (*str*) – of constant for registry
- **value** (*float, str, Constant, Quantity, Variable*) – expression for constant
- **registry** (*Registry*) – for storing define
- **addRegistry** (*bool*) – add constant to registry

**eval()**

Evaluate constant

**Returns** numerical evaluation of Constant

**Return type** float

**class** `pyg4ometry.gdml.Defines.Quantity`(*name, value, unit, type, registry, addRegistry=True*)

Bases: `pyg4ometry.gdml.Defines.ScalarBase`

GDML quantity define wrapper object

**Parameters**

- **name** (*str*) – of constant for registry
- **value** (*float, str, Constant, Quantity, Variable*) – expression for constant
- **unit** (*str*) – unit of the quantity
- **type** (*not sure*) – type of quantity
- **registry** (*Registry*) – for storing define
- **addRegistry** (*bool*) – add constant to registry

**eval()**

Evaluate quantity

**Returns** numerical evaluation of Quantity

**Return type** float

**class** `pyg4ometry.gdml.Defines.Variable`(*name, value, registry, addRegistry=True*)

Bases: `pyg4ometry.gdml.Defines.ScalarBase`

GDML variable define wrapper object

**Parameters**

- **name** (*str*) – of constant for registry
- **value** (*float, str, Constant, Quantity, Variable*) – expression for constant
- **registry** (*Registry*) – for storing define

**eval()**

Evaluate variable

**Returns** numerical evaluation of Constant

**Return type** float

**class** `pyg4ometry.gdml.Defines.Expression`(*name, value, registry, addRegistry=False*)

Bases: `pyg4ometry.gdml.Defines.ScalarBase`

General expression, does not have an analogue in GDML

**Parameters**

- **name** (*str*) – of constant for registry
- **value** (*float, str, Constant, Quantity, Variable*) – expression for constant
- **registry** (*Registry*) – for storing define
- **addRegistry** (*bool*) – add constant to registry

**eval()**

Evaluate expression

**Returns** numerical evaluation of Constant

**Return type** float

`pyg4ometry.gdml.Defines.sin(arg)`

Sin of a ScalarBase object, returns a Constant

**Parameters** `arg` (Constant, Quantity, Variable or Expression) – Argument of sin

`pyg4ometry.gdml.Defines.cos(arg)`

Cosine of a ScalarBase object, returns a Constant

**Parameters** `arg` (Constant, Quantity, Variable or Expression) – Argument of cos

`pyg4ometry.gdml.Defines.tan(arg)`

Tangent of a ScalarBase object, returns a Constant

**Parameters** `arg` (Constant, Quantity, Variable or Expression) – Argument of tan

`pyg4ometry.gdml.Defines.asin(arg)`

ArcSin of a ScalarBase object, returns a Constant

**Parameters** `arg` (Constant, Quantity, Variable or Expression) – Argument of asin

`pyg4ometry.gdml.Defines.acos(arg)`

ArcCos of a ScalarBase object, returns a Constant

**Parameters** `arg` (Constant, Quantity, Variable or Expression) – Argument of acos

`pyg4ometry.gdml.Defines.atan(arg)`

ArcTan of a ScalarBase object, returns a Constant

**Parameters** `arg` (Constant, Quantity, Variable or Expression) – Argument of tan

`pyg4ometry.gdml.Defines.exp(arg)`

Exponential of a ScalarBase object, returns a Constant

**Parameters** `arg` (Constant, Quantity, Variable or Expression) – Argument of exp

`pyg4ometry.gdml.Defines.log(arg)`

Natural logarithm of a ScalarBase object, returns a Constant

**Parameters** `arg` (Constant, Quantity, Variable or Expression) – Argument of log

`pyg4ometry.gdml.Defines.log10(arg)`

Base 10 logarithm of a ScalarBase object, returns a Constant

**Parameters** `arg` (Constant, Quantity, Variable or Expression) – Argument of log10

`pyg4ometry.gdml.Defines.sqrt(arg)`

Square root of a ScalarBase object, returns a Constant

**Parameters** `arg` (Constant, Quantity, Variable or Expression) – Argument of sin

**class** `pyg4ometry.gdml.Defines.VectorBase`

Bases: object

`__add__(other)`

`__mul__(other)`

`__rmul__ (other)`

`__sub__ (other)`

`eval ()`

Evaluate vector

**Returns** numerical evaluation of vector

**Return type** list of floats

`nonzero ()`

Evaluate vector

**Returns** Check if the vector is trivial (all elements zero)

**Return type** bool

`setName (name)`

Set name of vector

**Parameters** `name (str)` – name of object

`setRegistry (registry)`

**class** `pyg4ometry.gdml.Position (name, x, y, z, unit='mm', registry=None, addRegistry=True)`

Bases: `pyg4ometry.gdml.Defines.VectorBase`

GDML position define wrapper object

#### Parameters

- `x (float, Constant, Quantity, Variable)` – x component of position
- `y (float, Constant, Quantity, Variable)` – y component of position
- `z (float, Constant, Quantity, Variable)` – z component of position

**class** `pyg4ometry.gdml.Rotation (name, rx, ry, rz, unit='rad', registry=None, addRegistry=True)`

Bases: `pyg4ometry.gdml.Defines.VectorBase`

GDML rotation define wrapper object

#### Parameters

- `rx (float, Constant, Quantity, Variable)` – rotation around x axis
- `ry (float, Constant, Quantity, Variable)` – rotation around y axis
- `rz (float, Constant, Quantity, Variable)` – rotation around z axis

**class** `pyg4ometry.gdml.Scale (name, sx, sy, sz, unit=None, registry=None, addRegistry=True)`

Bases: `pyg4ometry.gdml.Defines.VectorBase`

GDML scale define wrapper object

#### Parameters

- `sx (float, Constant, Quantity, Variable)` – x component of scale
- `sy (float, Constant, Quantity, Variable)` – y component of scale
- `sz (float, Constant, Quantity, Variable)` – z component of scale

**class** `pyg4ometry.gdml.Matrix (name, coldim, values, registry, addRegistry=True)`

Bases: `object`

GDML matrix define wrapper object

#### Parameters

- `name (str)` – of constant for registry

- **coldim** – is number of columns
- **coldim** – int
- **values** (*list of float, str, Constant, Quantity, Variable*) – list of values for matrix
- **registry** (*Registry*) – for storing define
- **addRegistry** (*bool*) – add constant to registry

**eval()**

Evaluate matrix

**Returns** numerical evaluation of matrix

**Return type** numpy.array

`pyg4ometry.gdml.Defines.upgradeToVector (var, reg, type='position', addRegistry=False)`

Take a list [x,y,z] and create a vector

**Parameters**

- **var** (*list of str, float, Constant, Quantity, Variable*) – input list to create a position, rotation or scale
- **reg** (*Registry*) – registry
- **type** (*str*) – class type of vector (position, rotation, scale)
- **addRegistry** (*bool*) – flag to add to registry

`pyg4ometry.gdml.Defines.upgradeToTransformation (var, reg, addRegistry=False)`

Take a list of lists [[rx,ry,rz],[x,y,z]] and create a transformation [Rotation,Position]

**Parameters**

- **var** (*list of str, float, Constant, Quantity, Variable*) – input list to create a transformation
- **reg** (*Registry*) – registry
- **type** (*str*) – class type of vector (position, rotation, scale)
- **addRegistry** (*bool*) – flag to add to registry

## 8.2 Geant4 solids

**class** `pyg4ometry.geant4.solid.Plane.Plane (name, normal, dist, zlength=10000)`

Constructs a *infinite* plane. Should not be used to construct geant4 geometry.

**Parameters**

- **name** (*str*) – of object in registry
- **normal** (*tuple*) – normal [x,y,z]
- **dist** (*float*) – distance from origin to plane
- **zlength** (*float*) – large transverse box size to emulate infinite plane

**class** `pyg4ometry.geant4.solid.Wedge.Wedge (name, pRMax=1000, pSPhi=0, pDPhi=1.5, halfzlength=10000, nslice=None)`

Constructs a *infinite* wedge. Should not be used to construct geant4 geometry.

**Parameters**

- **name** (*str*) – of object in registry
- **normal** (*tuple*) – normal [x,y,z]
- **dist** (*float*) – distance from origin to plane

- **zlength** (*float*) – large transverse box size to emulate infinite plane

**class** pyg4ometry.geant4.solid.Box.**Box** (*name, pX, pY, pZ, registry, lunit='mm', addRegistry=True*)

Constructs a box. Note the lengths are full lengths and not half lengths as in Geant4

#### Parameters

- **name** (*str*) – of solid for registry
- **pX** (*float, Constant, Quantity, Variable, Expression*) – length along x
- **pY** (*float, Constant, Quantity, Variable, Expression*) – length along y
- **pZ** (*float, Constant, Quantity, Variable, Expression*) – length along z
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid

**class** pyg4ometry.geant4.solid.Tubs.**Tubs** (*name, pRMin, pRMax, pDz, pSPhi, pDPhi, registry, lunit='mm', aunit='rad', nslice=None, addRegistry=True*)

Constructs a cylindrical section.

#### Parameters

- **name** (*str*) – of solid for registry
- **pRMin** (*float, Constant, Quantity, Variable*) – inner radius
- **pRMax** (*float, Constant, Quantity, Variable*) – outer radius
- **pDz** (*float, Constant, Quantity, Variable*) – full length along z
- **pSPhi** (*float, Constant, Quantity, Variable*) – starting phi angle
- **pDPhi** (*float, Constant, Quantity, Variable*) – angle of segment in phi
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **aunit** (*str*) – angle unit (rad,deg) for solid
- **nslice** (*int*) – number of phi elements for meshing

**class** pyg4ometry.geant4.solid.CutTubs.**CutTubs** (*name, pRMin, pRMax, pDz, pSPhi, pDPhi, pLowNorm, pHighNorm, registry, lunit='mm', aunit='rad', nslice=None, addRegistry=True*)

Constructs a cylindrical section with end face cuts. Note pLowNorm and pHighNorm can be lists of floats, Constants, Quantities or Variables.

#### Parameters

- **name** (*str*) – of solid for registry
- **pRMin** (*float, Constant, Quantity, Variable*) – Inner radius
- **pRMax** (*float, Constant, Quantity, Variable*) – Outer radius
- **pDz** (*float, Constant, Quantity, Variable*) – length along z
- **pSPhi** (*float, Constant, Quantity, Variable*) – starting phi angle
- **pDPhi** (*float, Constant, Quantity, Variable*) – angle of segment
- **pLowNorm** (*list*) – normal vector of the cut plane at -pDz/2

- **pHighNorm** (*list*) – normal vector of the cut plane at +pDz/2

```
class pyg4ometry.geant4.solid.Cons.Cons (name, pRmin1, pRmax1, pRmin2, pRmax2,  
pDz, pSPhi, pDPhi, registry, lunit='mm', au-  
nunit='rad', nslice=None, addRegistry=True)
```

Constructs a conical section.

#### Parameters

- **name** (*str*) – of the solid
- **pRMin1** (*float, Constant, Quantity, Variable*) – inner radius at -pDz/2
- **pRMax1** (*float, Constant, Quantity, Variable*) – outer radius at -pDz/2
- **pRMin2** (*float, Constant, Quantity, Variable*) – inner radius at +pDz/2
- **pRMax2** (*float, Constant, Quantity, Variable*) – outer radius at +pDz/2
- **pDz** (*float, Constant, Quantity, Variable*) – length along z
- **pSPhi** (*float, Constant, Quantity, Variable*) – starting phi angle
- **pDPhi** (*float, Constant, Quantity, Variable*) – angle of segment in radians
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **aunit** (*str*) – angle unit (rad,deg) for solid
- **nslice** (*int*) – number of phi elements for meshing

```
class pyg4ometry.geant4.solid.Para.Para (name, pDx, pDy, pDz, pAlpha, pTheta, pPhi,  
registry, lunit='mm', aunit='rad', addReg-  
istry=True)
```

Constructs a parallelepiped.

#### Parameters

- **name** (*str*) – of the volume
- **pX** (*float, Constant, Quantity, Variable*) – length along x
- **pY** (*float, Constant, Quantity, Variable*) – length along y
- **pZ** (*float, Constant, Quantity, Variable*) – length along z
- **pAlpha** (*float, Constant, Quantity, Variable*) – angle formed by the y axis and the plane joining the centres of the faces parallel to the z-x plane at -dy/2 and +dy/2
- **pTheta** (*float, Constant, Quantity, Variable*) – polar angle of the line joining the centres of the faces at -dz/2 and +dz/2 in z
- **pPhi** (*float, Constant, Quantity, Variable*) – azimuthal angle of the line joining the centres of the faces at -dx/2 and +dx/2 in x
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **aunit** (*str*) – angle unit (rad,deg) for solid

```
class pyg4ometry.geant4.solid.Trd.Trd (name, pDx1, pDx2, pDy1, pDy2, pDz, registry, lu-  
nunit='mm', addRegistry=True)
```

Constructs a trapezoid.

**Parameters**

- **name** (*str*) – of the solid
- **pDx1** (*float*, *Constant*, *Quantity*, *Variable*) – length along x at the surface positioned at -dz/2
- **pDx2** (*float*, *Constant*, *Quantity*, *Variable*) – length along x at the surface positioned at +dz/2
- **pDy1** (*float*, *Constant*, *Quantity*, *Variable*) – length along y at the surface positioned at -dz/2
- **pDy2** (*float*, *Constant*, *Quantity*, *Variable*) – length along y at the surface positioned at +dz/2
- **dz** (*float*, *Constant*, *Quantity*, *Variable*) – length along the z axis
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid

```
class pyg4ometry.geant4.solid.Trap.Trap (name, pDz, pTheta, pDPhi, pDy1, pDx1, pDx2,  
                                         pAlp1, pDy2, pDx3, pDx4, pAlp2, registry, lunit='mm', aunit='rad', addRegistry=True)
```

```
class pyg4ometry.geant4.solid.Sphere.Sphere (name, pRmin, pRmax, pSPhi, pDPhi,  
                                             pSTheta, pDTheta, registry, lunit='mm',  
                                             aunit='rad', nslice=None, nstack=None,  
                                             addRegistry=True)
```

Constructs a section of a spherical shell.

**Parameters**

- **name** (*str*) – of object in registry
- **pRmin** (*float*, *Constant*, *Quantity*, *Variable*) – inner radius of the shell
- **pRmax** (*float*, *Constant*, *Quantity*, *Variable*) – outer radius of the shell
- **pSPhi** (*float*, *Constant*, *Quantity*, *Variable*) – starting phi angle in radians
- **pSTheta** (*float*, *Constant*, *Quantity*, *Variable*) – starting theta angle in radians
- **pDPhi** (*float*, *Constant*, *Quantity*, *Variable*) – delta phi angle in radians
- **pDTheta** (*float*, *Constant*, *Quantity*, *Variable*) – delta theta angle in radians
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **aunit** (*str*) – angle unit (rad,deg) for solid
- **nslice** (*int*) – number of phi elements for meshing
- **nstack** (*int*) – number of theta elements for meshing

**mesh** ()

working off  $0 < \phi < 2\pi$   $0 < \theta < \pi$

```
class pyg4ometry.geant4.solid.Orb.Orb (name, pRMax, registry, lunit='mm', nslice=None,  
                                       nstack=None, addRegistry=True)
```

Constructs a solid sphere.

**Parameters**



- **name** (*str*) – of the solid
- **pRMax** (*float, Constant, Quantity, Variable, Expression*) – outer radius
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **nslice** (*int*) – number of phi elements for meshing
- **nstack** (*int*) – number of theta elements for meshing

```
class pyg4ometry.geant4.solid.Torus.Torus (name, pRmin, pRmax, pRtor, pSPhi,  
pDPhi, registry, lunit='mm', aunit='rad',  
nslice=None, nstack=None, addReg-  
istry=True)
```

Constructs a torus.

#### Parameters

- **name** (*str*) – string, name of the volume
- **pRmin** (*float, Constant, Quantity, Variable, Expression*) – inner radius
- **pRmax** – outer radius
- **pRtor** (*float, Constant, Quantity, Variable, Expression*) – swept radius of torus
- **pSPhi** (*float, Constant, Quantity, Variable, Expression*) – start phi angle
- **pDPhi** (*float, Constant, Quantity, Variable, Expression*) – delta phi angle
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **aunit** (*str*) – angle unit (rad,deg) for solid
- **nslice** (*int*) – number of phi elements for meshing
- **nstack** (*int*) – number of theta elements for meshing

```
class pyg4ometry.geant4.solid.Polycone.Polycone (name, pSPhi, pDPhi, pZpl, pRMin,  
pRMax, registry, lunit='mm', au-  
nit='rad', nslice=None, addReg-  
istry=True)
```

Constructs a solid of rotation using an arbitrary 2D surface.

#### Parameters

- **name** (*str*) – of the solid
- **pSPhi** (*float, Constant, Quantity, Variable, Expression*) – starting rotation angle in radians
- **pDPhi** (*float, Constant, Quantity, Variable, Expression*) – total rotation angle in radius
- **pZPlns** (*list of float, Constant, Quantity, Variable, Expression*) – z-positions of planes used
- **pRInr** (*list of float, Constant, Quantity, Variable, Expression*) – inner radii of surface at each z-plane
- **pROut** (*list of float, Constant, Quantity, Variable, Expression*) – outer radii of surface at each z-plane

- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **aunit** (*str*) – angle unit (rad,deg) for solid
- **nslice** (*int*) – number of phi elements for meshing

Optional registration as this solid is used as a temporary solid in Polyhedra and needn't be always registered.

```
class pyg4ometry.geant4.solid.GenericPolycone.GenericPolycone (name, pSPhi,  
                                                             pDPhi, pR,  
                                                             pZ, registry,  
                                                             lunit='mm',  
                                                             aunit='rad',  
                                                             nslice=None,  
                                                             addReg-  
                                                             istry=True)
```

Constructs a solid of rotation using an arbitrary 2D surface defined by a series of (r,z) coordinates.

#### Parameters

- **name** (*str*) – of solid
- **pSPhi** (*float, Constant, Quantity, Variable, Expression*) – angle phi at start of rotation
- **pDPhi** (*float, Constant, Quantity, Variable, Expression*) – angle Phi at end of rotation
- **pR** (*list of float, Constant, Quantity, Variable, Expression*) – r coordinate
- **pZ** (*list of float, Constant, Quantity, Variable, Expression*) – z coordinate
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **aunit** (*str*) – angle unit (rad,deg) for solid
- **nslice** (*int*) – number of phi elements for meshing

```
class pyg4ometry.geant4.solid.Polyhedra.Polyhedra (name, pSPhi, pDPhi, num-  
                                                    Side, numZPlanes, zPlane,  
                                                    rInner, rOuter, registry,  
                                                    lunit='mm', aunit='rad',  
                                                    addRegistry=True)
```

Constructs a polyhedra.

#### Parameters

- **name** (*str*) – of solid
- **pSPhi** (*float, Constant, Quantity, Variable, Expression*) – start phi angle
- **pDPhi** (*float, Constant, Quantity, Variable, Expression*) – delta phi angle
- **numSide** (*int*) – number of sides
- **numZPlanes** (*int*) – number of planes along z
- **zPlane** (*list of float, Constant, Quantity, Variable, Expression*) – position of z planes
- **rInner** (*list of float, Constant, Quantity, Variable, Expression*) – tangent distance to inner surface per z plane

- **rOuter** (*list of float, Constant, Quantity, Variable, Expression*) – tangent distance to outer surface per z plane
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **aunit** (*str*) – angle unit (rad,deg) for solid

```
class pyg4ometry.geant4.solid.EllipticalTube.EllipticalTube (name, pDx, pDy,  
pDz, registry,  
lunit='mm',  
nstack=None,  
nslice=None,  
addRegistry=True)
```

Constructs a tube of elliptical cross-section.

#### Parameters

- **name** (*str*) – name of the solid
- **pDx** (*float, Constant, Quantity, Variable, Expression*) – length in x
- **pDy** (*float, Constant, Quantity, Variable, Expression*) – length in y
- **pDz** (*float, Constant, Quantity, Variable, Expression*) – length in z
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **nslice** (*int*) – number of phi elements for meshing
- **nstack** (*int*) – number of theta elements for meshing

**mesh()**

new meshing based of Tubs meshing

```
class pyg4ometry.geant4.solid.Ellipsoid.Ellipsoid (name, pxSemiAxis, pySemiAxis,  
pzSemiAxis, pzBottomCut, pzTopCut, registry, lunit='mm',  
nslice=None, nstack=None, addRegistry=True)
```

Constructs an ellipsoid optionally cut by planes perpendicular to the z-axis.

#### Parameters

- **name** (*str*) – of the solid
- **pxSemiAxis** (*float, Constant, Quantity, Variable, Expression*) – length of x semi axis
- **pySemiAxis** (*float, Constant, Quantity, Variable, Expression*) – length of y semi axis
- **pzSemiAxis** (*float, Constant, Quantity, Variable, Expression*) – length of z semi axis
- **pzBottomCut** (*float, Constant, Quantity, Variable, Expression*) – z-position of bottom cut plane
- **pzTopCut** (*float, Constant, Quantity, Variable, Expression*) – z-position of top cut plane
- **registry** (*Registry*) – for storing solid

- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **nslice** (*int*) – number of phi elements for meshing
- **nstack** (*int*) – number of theta elements for meshing

```
class pyg4ometry.geant4.solid.Paraboloid.Paraboloid(name, pDz, pR1, pR2,  
                                                    registry, lunit='mm',  
                                                    nslice=16, nstack=8,  
                                                    addRegistry=True)
```

Constructs a paraboloid with possible cuts along the z axis.

#### Parameters

- **name** (*str*) – of solid
- **pDz** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – length along z
- **pR1** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – radius at -Dz/2
- **pR2** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – radius at +Dz/2 (pR2 > pR1)
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **nslice** (*int*) – number of phi elements for meshing
- **nstack** (*int*) – number of theta elements for meshing

```
class pyg4ometry.geant4.solid.Hype.Hype(name, innerRadius, outerRadius, innerStereo,  
                                         outerStereo, lenZ, registry, lunit='mm', au-  
                                         nit='rad', nslice=None, nstack=None, ad-  
                                         dRegistry=True)
```

Constructs a tube with hyperbolic profile.

#### Parameters

- **name** (*str*) – of solid
- **innerRadius** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – inner radius
- **outerRadius** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – outer radius
- **innerStereo** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – inner stereo angle
- **outerStereo** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – outer stereo angle
- **lenZ** – length along z
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **anunit** (*str*) – angle unit (rad,deg) for solid
- **nslice** (*int*) – number of phi elements for meshing
- **nstack** (*int*) – number of theta elements for meshing

```
class pyg4ometry.geant4.solid.Tet.Tet(name, anchor, p2, p3, p4, registry, lunit='mm',  
                                       degeneracyFlag=False, addRegistry=True)
```

Constructs a tetrahedra.

#### Parameters

- **name** – of the solid
- **anchor** (*list*) – point 1 (anchor point)
- **p2** (*list*) – point 2
- **p3** (*list*) – point 3
- **p4** (*list*) – point 4
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **degeneracyFlag** – bool, indicates degeneracy of points

```
class pyg4ometry.geant4.solid.ExtrudedSolid.ExtrudedSolid(name, pPolygon,
                                                         pZslices, registry,
                                                         lunit='mm',
                                                         addRegistry=True)
```

Construct an extruded solid

#### Parameters

- **name** (*str*) – of solid
- **pPolygon** (*list of lists*) – x-y coordinates of vertices for the polygon.
- **pZslices** (*list of lists*) – z-coordinates of a slice, slice offsets in x-y and scaling
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid

Example: Triangular prism with 2 slices pPoligon = [[x1,y1],[x2,y2],[x3,v3]] - vertices of polygon in clockwise order zSlices = [[z1,[offsetx1, offsety1],scale1],[z2,[offsetx2, offsety2],scale2]]

```
class pyg4ometry.geant4.solid.TwistedBox.TwistedBox(name, twistedangle, pDx,
                                                    pDy, pDz, registry, lunit='mm',
                                                    aunit='rad', nstack=None,
                                                    refine=0, addRegistry=True)
```

Constructs a box that is twisted though angle twisted angle

#### Parameters

- **name** (*str*) – of the solid
- **twistedangle** (*float, Constant, Quantity, Variable, Expression*) – twist angle, must be less than pi/2
- **pDx** (*float, Constant, Quantity, Variable, Expression*) – length in x
- **pDy** (*float, Constant, Quantity, Variable, Expression*) – length in y
- **pDz** (*float, Constant, Quantity, Variable, Expression*) – length in z
- **refine** (*int*) – number of steps to iteratively smoothen the mesh by doubling the number of vertices at every step
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **aunit** (*str*) – angle unit (rad,deg) for solid
- **nstack** (*int*) – Not written

```
class pyg4ometry.geant4.solid.TwistedTrap.TwistedTrap(name, twistedAngle, pDz,
                                                    pTheta, pDPhi, pDy1,
                                                    pDx1, pDx2, pDy2, pDx3,
                                                    pDx4, pAlp, registry,
                                                    lunit='mm', aunit='rad',
                                                    nstack=None, addReg-
                                                    istry=True)
```

Constructs a general trapezoid with a twist around one axis.

#### Parameters

- **name** (*str*) – of the solid
- **twistedAngle** – angle of twist (<90 deg)
- **pDz** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – length along z
- **pDx1** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – length along x of the side at y=-pDy1/2
- **pDx2** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – length along x of the side at y=+pDy1/2
- **pTheta** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – polar angle of the line joining the centres of the faces at -/+pDz/2
- **pPhi** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – azimuthal angle of the line joining the centres of the faces at -/+pDz/2
- **pDy1** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – length at -pDz/2
- **pDy2** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – length at +pDz/2
- **pDx3** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – length of the side at y=-pDy2 of the face at +pDz/2
- **pDx4** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – length of the side at y=+pDy2 of the face at +pDz/2
- **pAlp** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – angle wrt the y axi from the centre of the side
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **aunit** (*str*) – angle unit (rad,deg) for solid

```
class pyg4ometry.geant4.solid.TwistedTrd.TwistedTrd(name, twistedangle, pDx1,
                                                    pDx2, pDy1, pDy2, pDz,
                                                    registry, lunit='mm', au-
                                                    nit='rad', nstack=None, re-
                                                    fine=0, addRegistry=True)
```

Constructs a twisted general trapezoid.

#### Parameters

- **name** (*str*) – of solid
- **twistedangle** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – twist angle, must be less than 0.5\*pi
- **pDx1** (*float*, *Constant*, *Quantity*, *Variable*, *Expression*) – length in x at surface positioned at -pDz/2

- **pDx2** (*float, Constant, Quantity, Variable, Expression*) – length in x at surface positioned at +pDz/2
- **pDy1** (*float, Constant, Quantity, Variable, Expression*) – length in y at surface positioned at -pDz/2
- **pDy2** (*float, Constant, Quantity, Variable, Expression*) – length in y at surface positioned at +pDz/2
- **pDz** (*float, Constant, Quantity, Variable, Expression*) – length in z
- **refine** (*int*) – number of steps to iteratively smoothen the mesh by doubling the number of vertices at every step
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **aunit** (*str*) – angle unit (rad,deg) for solid
- **nstack** (*int*) – number of theta elements for meshing

```
class pyg4ometry.geant4.solid.TwistedTubs.TwistedTubs (name, endinnerrad,
                                                         endouterrad, zlen,
                                                         phi, twistedangle, reg-
                                                         istry, lunit='mm', au-
                                                         nit='rad', nslice=None,
                                                         nstack=None, addReg-
                                                         istry=True)
```

Creates a twisted tube segment. Note that only 1 constructor is supported.

#### Parameters

- **name** (*str*) – of solid
- **endinnerrad** (*float, Constant, Quantity, Variable, Expression*) – inner radius at the end of the segment
- **endinnerrad** – outer radius at the end of the segment
- **zlen** (*float, Constant, Quantity, Variable, Expression*) – length of the tube segment
- **twistedangle** (*float, Constant, Quantity, Variable, Expression*) – twist angle
- **registry** (*Registry*) – for storing solid
- **lunit** (*str*) – length unit (nm,um,mm,m,km) for solid
- **aunit** (*str*) – angle unit (rad,deg) for solid
- **nslice** – number of phi elements for meshing
- **nstack** (*int*) – number of theta elements for meshing

```
class pyg4ometry.geant4.solid.GenericTrap.GenericTrap (name, v1x, v1y, v2x, v2y,
                                                         v3x, v3y, v4x, v4y, v5x,
                                                         v5y, v6x, v6y, v7x, v7y,
                                                         v8x, v8y, dz, registry,
                                                         nstack=20, lunit='mm',
                                                         addRegistry=True)
```

Constructs an arbitrary trapezoid using two quadrilaterals sitting on two parallel planes. Vertices 1-4 define the quadrilateral at -dz and vertices 5-8 define the quadrilateral at +dz. This solid is called Arb8 in GDML notation.

#### Parameters

- **name** – string, name of the volume

- **v1x** – vertex 1 x position
- **v1y** – vertex 1 y position
- **v2x** – vertex 2 x position
- **v2y** – vertex 2 y position
- **v3x** – vertex 3 x position
- **v3y** – vertex 3 y position
- **v4x** – vertex 4 x position
- **v4y** – vertex 4 y position
- **v5x** – vertex 5 x position
- **v5y** – vertex 5 y position
- **v6x** – vertex 6 x position
- **v6y** – vertex 6 y position
- **v7x** – vertex 7 x position
- **v7y** – vertex 7 y position
- **v8x** – vertex 8 x position
- **v8y** – vertex 8 y position
- **dz** – half length along z
- **registry** ([Registry](#)) – for storing solid

```
class pyg4ometry.geant4.solid.TessellatedSolid.TessellatedSolid(name,  
                                                                meshTess,  
                                                                registry,  
                                                                meshtype=1,  
                                                                addReg-  
                                                                istry=True)
```

Constructs a tessellated solid

#### Parameters

- **name** (*str*) – of solid
- **mesh** (*Freecad, Gdml or Stl*) – mesh
- **registry** ([Registry](#)) – for storing solid
- **meshtype** (*MeshType.Freecad*) – type of mesh

```
pyg4ometry.geant4.solid.TessellatedSolid.createTessellatedSolid(name,  
                                                                polygons,  
                                                                reg)
```

**Args:** name: Name of the tessallated solid polygons: list of polygons (list of points given in clockwise order). All polygons should have the same number of points. reg: registry

Returns: TessellatedSolid

```
class pyg4ometry.geant4.solid.Union.Union(name, obj1, obj2, tra2, registry, addReg-  
                                          istry=True)
```

Union between two solids

#### Parameters

- **name** (*str*) – of solid
- **obj1** (*pyg4ometry.geant4.solid*) – unrotated, untranslated solid



- **obj2** (*pyg4ometry.geant4.solid*) – solid rotated and translated according to *tra2*
- **tra2** (*list*) – [rot,tra] = [[a,b,g],[dx,dy,dz]]
- **registry** (*Registry*) – for storing solid

```
class pyg4ometry.geant4.solid.Intersection.Intersection(name, obj1, obj2,
                                                         tra2, registry, addRegistry=True)
```

Intersection between two solids

#### Parameters

- **name** (*str*) – of solid
- **obj1** (*pyg4ometry.geant4.solid*) – unrotated, untranslated solid
- **obj2** (*pyg4ometry.geant4.solid*) – solid rotated and translated according to *tra2*
- **tra2** (*list*) – [rot,tra] = [[a,b,g],[dx,dy,dz]]
- **registry** (*Registry*) – for storing solid

```
class pyg4ometry.geant4.solid.Subtraction.Subtraction(name, obj1, obj2,
                                                         tra2, registry, addRegistry=True)
```

Subtraction between two solids

#### Parameters

- **name** (*str*) – of solid
- **obj1** (*pyg4ometry.geant4.solid*) – unrotated, untranslated solid
- **obj2** (*pyg4ometry.geant4.solid*) – solid rotated and translated according to *tra2*
- **tra2** (*list*) – [rot,tra] = [[a,b,g],[dx,dy,dz]]
- **registry** (*Registry*) – for storing solid

## 8.3 Geant4 module

```
class pyg4ometry.geant4.Registry
```

Bases: *object*

Object to store geometry for input and output. All of the pyg4ometry classes can be used without storing them in the Registry. The registry is used to write the GDML output file. A registry needs to be used in conjunction with gdml Define objects for evaluation of expressions.

```
addDefine (define, namePolicy='none')
```

Parameters **define** (*Constant*, *Quantity*, *Variable*, *Matrix*) – Definition object for storage

```
addLogicalVolume (volume, namePolicy='none')
```

Parameters **volume** (*LogicalVolume*) – LogicalVolume object for storage

```
addMaterial (material, namePolicy='reuse')
```

Parameters **material** (*Material*) – Material object for storage

```
addPhysicalVolume (volume, namePolicy='increment')
```

Parameters **volume** (*PhysicalVolume*) – PhysicalVolume object for storage

```
addSolid (solid, namePolicy='none')
```

**Parameters** **solid** (*One of the geant4 solids*) – Solid object for storage

`pyg4ometry.geant4.AnalyseGeometryComplexity` (*logicalVolume*)

Analyse a geometry tree starting from a logical volume. Produces an instance of `GeometryComplexityInformation` with summary information. Provides:

- count per solid type
- number of daughters per logical volume
- dictionary of N daughters for each logical volume name
- depth count of Boolean solids

ie a Boolean of a Boolean returns 2, a Boolean of two primitives returns 1

- a dictionary of boolean depth for each logical volume name

Example:

```
info = AnalyseGeometryComplexity(lv)
info.printSummary()
```

**class** `pyg4ometry.geant4.Material` (*\*\*kwargs*)

Bases: `pyg4ometry.geant4._Material.MaterialBase`

This class provides an interface to GDML material definitions.

Because of the different options for constructing a material instance the constructor is kward only. Proxy methods are provided to instantiate particular types of material. Those proxy methods are:

`MaterialSingleElement` `MaterialCompound` `MaterialPredefined`

It is possible to instantiate a material directly through kwargs. The possible kwargs are (but note some are mutually exclusive): `name` - string `density` - float `atomic_number` - int `atomic_weight` - float `number_of_components` - int `state` - string `pressure` - float `pressure_unit` - string `temperature` - float `temperature_unit` - string

**add\_element\_massfraction** (*element, massfraction*)

Add an element as a component to a material as a fraction of the material mass. Can only add elements to materials defined as composite.

**Inputs:** `element` - `pyg4ometry.geant4.Material.Element` instance `massfraction` - float,  $0.0 < \text{massfraction} \leq 1.0$

**add\_element\_natoms** (*element, natoms*)

Add an element as a component to a material as a number of atoms in the material molecule. Can only add elements to materials defined as composite.

**Inputs:** `element` - `pyg4ometry.geant4.Material.Element` instance `natoms` - int, number of atoms in the compound molecule

**add\_material** (*material, fractionmass*)

Add a material as a component to another material (mixture) as a fraction of the mixture mass. Can only add new materials to materials defined as composite.

**Inputs:** `material` - `pyg4ometry.geant4.Material.Material` instance `massfraction` - float,  $0.0 < \text{massfraction} \leq 1.0$

**add\_property** (*name, value*)

**set\_pressure** (*value, unit='pascal'*)

**set\_temperature** (*value, unit='K'*)

**state\_variables**

```
class pyg4ometry.geant4.LogicalVolume.LogicalVolume (solid, material, name,  
                                                    registry=None, addReg-  
                                                    istry=True, **kwargs)
```

Bases: object

LogicalVolume : G4LogicalVolume :param solid: :param material: :param name: :param registry: :param addRegistry:

**add** (*physicalVolume*)

**addAuxiliaryInfo** (*auxiliary*)

**addBDSIMObject** (*bdsimobject*)

**assemblyVolume** ()

**checkOverlaps** (*recursive=False, coplanar=True, debugIO=False, printOut=True, nOverlaps-*  
*Detected=[0]*)

Check based on the meshes in each logical volume if there are any geometrical overlaps. By default, overlaps are checked between daughter volumes and with the mother volume itself (protrusion). Coplanar overlaps may also be checked (default on).

Print out will be given for any overlaps detected and the visualiser will show the colour coded overlaps.

#### Parameters

- **recursive** – bool - Whether to descend into the daughter volumes and check their contents also.
- **coplanar** – bool - Whether to check for coplanar overlaps
- **debugIO** – bool - Print out for every check made
- **printOut** – bool - (internal) Whether to print out a summary of N overlaps detected
- **nOverlapsDetected** – [int] - (internal) counter for recursion - ignore

**clipSolid** (*lengthSafety=1e-06*)

**cullDaughtersOutsideSolid** (*solid, rotation=None, position=None*)

Given a solid with a placement rotation and position inside this logical volume, remove (cull) any daughters that would not lie entirely within it.

**extent** (*includeBoundingSolid=False*)

**findLogicalByName** (*name*)

**makeLogicalPhysicalNameSets** ()

**makeMaterialNameSet** ()

**makeSolidTessellated** ()

**makeWorldVolume** (*worldMaterial='G4\_Galactic'*)

**setSolid** (*solid*)

```
class pyg4ometry.geant4.PhysicalVolume.PhysicalVolume (rotation, position, logi-  
                                                    calVolume, name, moth-  
                                                    erVolume, registry=None,  
                                                    addRegistry=True,  
                                                    scale=None)
```

Bases: object

PhysicalVolume : G4VPhysicalVolume, G4PVPlacement

#### Parameters

- **rotation** – [float,float,float] - rotations about x,y,z axes of mother volume
- **position** – [float,float,float] - translation with respect to mother volume
- **logicalVolume** – *pyg4ometry.geant4.LogicalVolume* - instance to place

- **name** – str - name of this placement
- **motherVolume** – `pyg4ometry.geant4.LogicalVolume` - mother volume to place into
- **registry** – `pyg4ometry.geant4.Registry` - registry to register to
- **addRegistry** – bool - whether to add to the registry or not

**extent** (*includeBoundingSolid=True*)

```
class pyg4ometry.geant4.ReplicaVolume.ReplicaVolume(name, logicalVolume, motherVolume, axis, nreplicas, width, offset=0, registry=None, addRegistry=True, wunit='mm', ounit='mm')
```

Bases: `pyg4ometry.geant4.PhysicalVolume.PhysicalVolume`

ReplicaVolume: G4PVR replica

#### Parameters

- **name** – of physical volume
- **logical** – volume to be placed
- **mother** – logical volume,
- **axis** – kXAxis, kYAxis, kZAxis, kRho, kPhi
- **ncopies** – number of replicas
- **width** – spacing between replicas along axis
- **offset** – of grid

```
class Axis
```

Bases: object

```
kPhi = 5
```

```
kRho = 4
```

```
kXAxis = 1
```

```
kYAxis = 2
```

```
kZAxis = 3
```

```
createReplicaMeshes()
```

**extent** (*includeBoundingSolid=True*)

```
getPhysicalVolumes()
```

return a list of temporary (ie not added to the relevant registry) `PhysicalVolume` instances with appropriate transforms including any daughter `ReplicaVolumes`.

The exception is for kRho axis where new unique solids and logical volumes are required. Therefore, these are added to the registry and inadvertently to the mother LV as PVS.

```

class pyg4ometry.geant4.ParameterisedVolume.ParameterisedVolume (name,
                                                                    logicalVol-
                                                                    ume,
                                                                    mother-
                                                                    Volume,
                                                                    ncopies,
                                                                    param-
                                                                    Data,
                                                                    trans-
                                                                    forms, reg-
                                                                    istry=None,
                                                                    addReg-
                                                                    istry=True)

```

Bases: `pyg4ometry.geant4.ReplicaVolume.ReplicaVolume`

ParametrisedVolume :param name: of parametrised volume :type name: str :param logical: volume to be placed :type logical: logicalVolume :param mother: volume logical volume :type mother: logicalVolume :param ncopies: number of parametrised volumes :type ncopies: int

```

class BoxDimensions (pX, pY, pZ, lunit='mm')

```

Bases: object

```

class ConeDimensions (pRMin1, pRMax1, pRMin2, pRMax2, pDz, pSPhi, pDPhi, lunit='mm',
                      aunit='rad')

```

Bases: object

```

class EllipsoidDimensions (pxSemiAxis, pySemiAxis, pzSemiAxis, pzBottomCut, pzTopCut,
                           lunit='mm')

```

Bases: object

```

class HypeDimensions (innerRadius, outerRadius, innerStereo, outerStereo, lenZ, lunit='mm',
                     aunit='rad')

```

Bases: object

```

class OrbDimensions (pRMax, lunit='mm')

```

Bases: object

```

class ParaDimensions (pX, pY, pZ, pAlpha, pTheta, pPhi, lunit='mm', aunit='rad')

```

Bases: object

```

class PolyconeDimensions (pSPhi, pDPhi, pZpl, pRMin, pRMax, lunit='mm', aunit='rad')

```

Bases: object

```

class PolyhedraDimensions (pSPhi, pDPhi, numSide, pZpl, pRMin, pRMax, lunit='mm',
                           aunit='rad')

```

Bases: object

```

class SphereDimensions (pRMin, pRMax, pSPhi, pDPhi, pSTheta, pDTheta, lunit='mm',
                        aunit='rad')

```

Bases: object

```

class TorusDimensions (pRMin, pRMax, pRTor, pSPhi, pDPhi, lunit='mm', aunit='rad')

```

Bases: object

```

class TrapDimensions (pDz, pTheta, pDPhi, pDy1, pDx1, pDx2, pAlp1, pDy2, pDx3, pDx4,
                      pAlp2, lunit='mm', aunit='rad')

```

Bases: object

```

class TrdDimensions (pX1, pX2, pY1, pY2, pZ, lunit='mm')

```

Bases: object

```

class TubeDimensions (pRMin, pRMax, pDz, pSPhi, pDPhi, lunit='mm', aunit='rad')

```

Bases: object

```

createParameterisedMeshes ()

```

```

extent (includeBoundingSolid=True)

```

## 8.4 VTK module

**class** pyg4ometry.visualisation.VtkViewer.**MouseInteractorNamePhysicalVolume** (*renderer, vtkviewer*)

Bases: vtkmodules.vtkInteractionStyle.vtkInteractorStyleTrackballCamera

**rightButtonPressEvent** (*obj, event*)

pyg4ometry.visualisation.VtkViewer.**PubViewer**

alias of *pyg4ometry.visualisation.VtkViewer.VtkViewerColoured*

**class** pyg4ometry.visualisation.VtkViewer.**VtkViewer** (*size=(1024, 1024), interpolation='none', \*\*kwargs*)

Bases: object

Visualiser.

### Parameters

- **size** – (int,int) - (nPixelsHorizontal, nPixelsVeritcal), default (1024,1024)
- **interpolation** – (str) - one of “none”, “flat”, “gouraud”, “phong”

### Examples

```
>>> v = VtkViewer()
>>> v.addLogicalVolume(someLV)
>>> v.view()
```

**addAxes** (*length=20.0, origin=(0, 0, 0)*)

Add x,y,z axis to the scene.

### Parameters

- **length** – float - length of each axis in mm
- **origin** – (float,float,float) - (x,y,z) of origin in mm

**addAxesWidget** ()

**addBooleanSolidRecursive** (*solid, mtra=matrix([[1, 0, 0], [0, 1, 0], [0, 0, 1]]), tra=array([0, 0, 0]), first=True*)

**addCutterPlane** (*position, normal, colour=None*)

Add a cutting plane at position=[x,y,z] with normal [nx,ny,nz].

### Parameters

- **position** – [float, float, float] - (x,y,z) poisition in scene (mm)
- **normal** – [float, float, float] - (nx,ny,z) normal unit vector
- **colour** – None or [float, float, float] - [r,g,b] in range [0:1]

Cutters are stored in self.usercutters.

**addLogicalVolume** (*logical, mtra=matrix([[1, 0, 0], [0, 1, 0], [0, 0, 1]]), tra=array([0, 0, 0])*)

**addLogicalVolumeBounding** (*logical*)

**addLogicalVolumeRecursive** (*logical, mtra=matrix([[1, 0, 0], [0, 1, 0], [0, 0, 1]]), tra=array([0, 0, 0])*)

**addMaterialVisOption** (*materialName, visOptionInstance*)

Append a visualisation option instance to the dictionary of materials.

### Parameters

- **materialName** – str - material name to match
- **visOptionInstance** – VisualisationOptions instance

**addMesh** (*pv\_name, solid\_name, mesh, mtra, tra, localmeshes, filters, mappers, mapperMap, actors, actorMap, visOptions=None, overlap=False, cutters=True, clippers=False*)

**addMeshSimple** (*csgMesh, visOptions=<VisOpt: rep=surface, rgba=[0.5, 0.5, 0.5, 0.5], vis=True, linewidth=1>, clip=False*)

**exportCutterSection** (*filename, normal='x', scaling=1.0*)

Export the section lines in plane perpendicular to normal. Exported as json text.

#### Parameters

- **filename** – (str) - name of file to export to
- **normal** – (str) - one of “x”, “y” or “z”
- **scaling** – (float) - multiplier for all cutter line coordinates on export

#### Examples

```
>>> v.exportCutterSection("xz-section.dat", normal="y", scaling=1000)
```

**exportGLTFScene** (*fileName='scene.glTF'*)

**exportOBJScene** (*fileName='scene'*)

**exportScreenShot** (*fileName='screenshot.png', rgba=True*)

Write the render window view to an image file.

Image types supported are: BMP, JPEG, PNM, PNG, PostScript, TIFF. The default parameters are used for all writers, change as needed.

#### Parameters

- **fileName** – The file name, if no extension then PNG is assumed.
- **renWin** – The render window.
- **rgba** – Used to set the buffer type.

#### Returns

**exportVRMLScene** (*fileName='scene'*)

**getMaterialVisOptions** (*pv*)

**getOverlapVisOptions** (*overlaptype*)

**printViewParameters** ()

**setCameraFocusPosition** (*focalPoint=[0, 0, 0], position=[100, 100, 100]*)

**setCutterNormal** (*dimension, normal*)

#### Parameters

- **dimension** – str - ‘x’, ‘y’, or ‘z’
- **normal** – list([x,y,z]) - should be unit vector

**setCutterOrigin** (*dimension, origin*)

#### Parameters

- **dimension** – str - ‘x’, ‘y’, or ‘z’
- **origin** – list([x,y,z])

**setMaterialVisOptions** (*materialDict*)

Replace the (by default None) dictionary for materials to colours :param materialDict: {“material-Name”: VisualisationOptions}

See also VisualisationOptions.

**setOpacity** (*v, iActor=-1*)

```
setOpacityOverlap (v, iActor=-1)
setRandomColours (seed=0)
setSurface (iActor=-1)
setSurfaceOverlap (iActor=-1)
setWireframe (iActor=-1)
setWireframeOverlap (iActor=-1)
start ()
view (interactive=True, resetCamera=True)
viewSection (dir='x')
```

```
class pyg4ometry.visualisation.VtkViewer.VtkViewerColoured(*args, default-
    Colour=None,
    materialVisOptions=None,
    **kwargs)
```

Bases: `pyg4ometry.visualisation.VtkViewer.VtkViewer`

Visualiser that extends `VtkViewer`. Uses “flat” interpolation and introduces control over colours.

#### Keyword Arguments

- **materialVisOptions**: {“materialName”: VisualisationOptions or list or tuple, ...}
- **interpolation** (str): see `VtkViewer`
- **defaultColour** (str): “random” or [r,g,b]

#### Examples

```
>>> vMaterialMap = VtkViewerColoured(materialVisOptions={"G4_WATER": [0, 0, 1]})
>>> vRandom = VtkViewerColoured(defaultColour="random")
>>> vColoured = VtkViewerColoured(defaultColour=[0.1, 0.1, 0.1])
>>> vColourAlpha = VtkViewerColoured(defaultColour=[0.1, 0.1, 0.1, 0.5])
```

of use visualisation options instances

```
>>> vo = pyg4ometry.visualisation.VisualisationOptions()
>>> vo.colour = [0.1, 1.0, 0.5]
>>> vo.alpha = 0.3
>>> options = {'G4_WATER': vo}
>>> vis = VtkViewerColoured(materialVisOptions=options)
```

If the value in the `materialVisOptions` is a list or a tuple, it will be upgraded to a `VisualisationOptions` instance.

```
class pyg4ometry.visualisation.VtkViewer.VtkViewerColouredMaterial(*args,
    **kwargs)
```

Bases: `pyg4ometry.visualisation.VtkViewer.VtkViewerColoured`

Extension of `VtkViewerColoured` that uses a default material dictionary for several common materials. Material colours are in defined `Colour.py` for many Geant4, FLUKA and BDSIM materials.

```
pyg4ometry.visualisation.VtkViewer.axesFromExtents (extent)
```

## 8.5 Freecad module

```
pyg4ometry.freecad.Reader.FacetListAxisAlignedExtent (facetList)
```

```
pyg4ometry.freecad.Reader.MeshAnalysis (m)
```



```

pyg4ometry.freecad.Reader.MeshCleaning (m)
pyg4ometry.freecad.Reader.MeshToFacetList (mesh)
pyg4ometry.freecad.Reader.PartFeatureGlobalPlacement (obj, placement)
class pyg4ometry.freecad.Reader.Reader (fileName, registryOn=True, file-
NameAux=None)
    Bases: object
    convertFlat (meshDeviation=0.05, centreName="", globalOffset=Vector (0.0, 0.0, 0.0), glob-
alRotation=Rotation (0.0, 0.0, 0.0, 1.0), extentScale=1.0, daughterMate-
rial='G4_Galactic', storePartCentrePos=False, meshShrinkFactor=1e-06)
        Convert file without structure
    convertStructure ()
        Convert file with structure
    getRegistry ()
    load (fileName)
    loadAuxiliaryData (fileName, colorByMaterial=True)
    printPartFeatures (fileName=None, randomColors=False)
        Print to screen or write to file Part::Features with color and material
    printStructure ()
    recurseObjectTree (obj)
    recursePrintObjectTree (obj)
    relabelModel ()
    setLogicalVolumeMaterial (logicalVolumeName, material='G4_Galactic')
    simplifyModel (volumeCut=500000.0)
pyg4ometry.freecad.Reader.WriteSMeshFile (mesh, filename)

```

## 8.6 STL module

```

class pyg4ometry.stl.Reader.Reader (filename, solidname='stl_tessellated', scale=1, reg-
istry=None)
    Bases: object
    getRegistry ()
    getSolid ()
    load ()
    visualise ()
        View solid directly by using a dummy world
    writeDefaultGDML (filename='default', gmad_tester=False)
        Write the tessellated solid loaded from STL to GDML. The placement has no rotation or translation.
        The world material is G4_Galactic, the solid material is G4_Fe.

```

## 8.7 GDML module

```

class pyg4ometry.gdml.Reader.Reader (fileName, registryOn=True)
    Bases: object
    extractStructureNodeData (node)
    getRegistry ()

```

`load()`  
`parseBox (node)`  
`parseCone (node)`  
`parseCutTube (node)`  
`parseDefines (xmldoc)`  
`parseEllipsoid (node)`  
`parseEllipticalCone (node)`  
`parseEllipticalTube (node)`  
`parseExtrudedSolid (node)`  
`parseGenericPolycone (node)`  
`parseGenericPolyhedra (node)`  
`parseGenericTrap (node)`  
`parseHype (node)`  
`parseIntersection (node)`  
`parseMaterials (xmldoc)`  
`parseMultiUnion (node)`  
`parseOpticalSurface (node)`  
`parseOrb (node)`  
`parsePara (node)`  
`parseParaboloid (node)`  
`parsePhysicalVolumeChildren (node, vol)`  
`parsePolycone (node)`  
`parsePolyhedra (node)`  
`parseScaledSolid (node)`  
`parseSolidLoop (node)`  
`parseSolids (xmldoc)`  
`parseSphere (node)`  
`parseStructure (xmldoc)`  
`parseSubtraction (node)`  
`parseTessellatedSolid (node)`  
`parseTet (node)`  
`parseTorus (node)`  
`parseTrap (node)`  
`parseTrd (node)`  
`parseTube (node)`  
`parseTwistedBox (node)`  
`parseTwistedTrap (node)`  
`parseTwistedTrd (node)`  
`parseTwistedTubs (node)`

```

    parseUnion (node)
    parseUserInfo (xml doc)
    parseVector (node, type='position', addRegistry=True)
class pyg4ometry.gdml.Writer.Writer (prepend="")
    Bases: object
    addDetector (registry)
    checkDefineName (defineName)
    checkLogicalVolumeName (logicalVolumeName)
    checkMaterialName (materialName)
    checkPhysicalVolumeName (physicalVolumeName)
    checkSolidName (solidName)
    createPosition (name, x, y, z)
    createQuadrangularFacet (vertex1, vertex2, vertex3, vertex4)
    createSection (zOrder, zPosition, xOffset, yOffset, scalingFactor)
    createTriangularFacet (vertex1, vertex2, vertex3)
    createTwoDimVertex (x, y)
    creatorzPoint (r, z)
    createzPlane (rInner, rOuter, zplane)
    getValueOrExpr (var)
    getValueOrExprFromInstance (instance, variable, index=None)
    write (filename)
    writeAssemblyVolume (lv)
    writeAuxiliary (aux, parent=None)
    writeBorderSurface (instance)
    writeBox (instance)
    writeCons (instance)
    writeCutTubs (instance)
    writeDefaultLattice (filename='lattice.gmad')
    writeDefine (define)
    writeDivisionVolume (instance)
    writeEllipsoid (instance)
    writeEllipticalCone (instance)
    writeEllipticalTube (instance)
    writeExtrudedSolid (instance)
    writeGMADTesterNoBeamline (gmad, gdml)
    writeGenericPolycone (instance)
    writeGenericPolyhedra (instance)
    writeGenericTrap (instance)
    writeGmadTester (filenameGmad, filenameGDML, writeDefaultLattice=False, preprocess-
        GDML=True)

```

**writeHype** (*instance*)

**writeIntersection** (*instance*)

**writeLogicalVolume** (*lv*)

**writeMaterial** (*material*)

**writeMultiUnion** (*instance*)

**writeOpticalSurface** (*instance*)

**writeOrb** (*instance*)

**writePara** (*instance*)

**writeParaboloid** (*instance*)

**writeParametrisedVolume** (*instance*)

**writePhysicalVolume** (*pv*)

**writePolycone** (*instance*)

**writePolyhedra** (*instance*)

**writeReplicaVolume** (*instance*)

**writeScaled** (*instance*)

**writeSkinSurface** (*instance*)

**writeSolid** (*solid*)

Dispatch to correct member function based on type string in SolidBase.

**writeSphere** (*instance*)

**writeSubtraction** (*instance*)

**writeTessellatedSolid** (*instance*)

**writeTet** (*instance*)

**writeTorus** (*instance*)

**writeTrap** (*instance*)

**writeTrd** (*instance*)

**writeTubs** (*instance*)

**writeTwistedBox** (*instance*)

**writeTwistedTrap** (*instance*)

**writeTwistedTrd** (*instance*)

**writeTwistedTubs** (*instance*)

**writeUnion** (*instance*)

**writeVectorVariable** (*node, vector\_var, allow\_ref=True, suppress\_trivial=True*)

Writes an XML child node for a vector variable - position, rotation, scale. If *allow\_ref* is enabled, it will write a ref to a registry define where possible. If *suppress\_trivial* is enabled it won't write vectors with all elements zero.

## 8.8 Fluka bodies

Set of classes for FLUKA bodies.

```
class pyg4ometry.fluka.body.RPP(name, xmin, xmax, ymin, ymax, zmin, zmax, transform=None, flukaregistry=None, addRegistry=True, comment="")
```

Bases: `pyg4ometry.fluka.body.BodyMixin`

Rectangular Parallelepiped

#### Parameters

- **name** (*str*) – of body
- **xmin** (*float*) – lower x coordinate of RPP
- **xmax** (*float*) – upper x coordinate of RPP
- **ymin** (*float*) – lower y coordinate of RPP
- **ymax** (*float*) – upper y coordinate of RPP
- **zmin** (*float*) – lower z coordinate of RPP
- **zmax** (*float*) – upper z coordinate of RPP

**\_withLengthSafety** (*safety, reg*)

**centre** (*aabb=None*)

**flukaFreeString** ()

**geant4Solid** (*reg, aabb=None*)

**lengths** ()

**rotation** ()

```
class pyg4ometry.fluka.body.BOX(name, vertex, edge1, edge2, edge3, transform=None, flukaregistry=None, comment="")
```

Bases: `pyg4ometry.fluka.body.BodyMixin`

General Rectangular Parallelepiped

#### Parameters

- **name** (*str*) – of body
- **vertex** (*list*) – position [x, y, z] of one of the corners.
- **edge1** (*list*) – vector [x, y, z] denoting the first side of the box.
- **edge2** (*list*) – vector [x, y, z] denoting the second side of the box.
- **edge3** (*list*) – vector [x, y, z] denoting the second side of the box.

**\_withLengthSafety** (*safety, reg*)

**centre** (*aabb=None*)

**flukaFreeString** ()

**geant4Solid** (*greg, aabb=None*)

**lengths** ()

**rotation** ()

```
class pyg4ometry.fluka.body.SPH(name, point, radius, transform=None, flukaregistry=None, comment="")
```

Bases: `pyg4ometry.fluka.body.BodyMixin`

Sphere

#### Parameters

- **name** (*str*) – of body
- **point** (*list*) – position [x, y, z] of the centre of the sphere.

- **radius** (*float*) – radius of the sphere.

**\_withLengthSafety** (*safety, reg*)

**centre** (*aabb=None*)

**flukaFreeString** ()

**geant4Solid** (*reg, aabb=None*)

**rotation** ()

**class** pyg4ometry.fluka.body.**RCC** (*name, face, direction, radius, transform=None, flukaregistry=None, comment=""*)

Bases: pyg4ometry.fluka.body.BodyMixin

Right Circular Cylinder

#### Parameters

- **name** (*str*) – of body
- **vertex** (*list*) – position [x, y, z] of one of the faces of the cylinder.
- **edge1** (*list*) – vector [x, y, z] denoting the direction along the length of the cylinder.
- **edge2** (*float*) – radius of the cylinder face.

**\_withLengthSafety** (*safety, reg*)

**centre** (*aabb=None*)

**flukaFreeString** ()

**geant4Solid** (*reg, aabb=None*)

**rotation** ()

**class** pyg4ometry.fluka.body.**REC** (*name, face, direction, semiminor, semimajor, transform=None, flukaregistry=None, comment=""*)

Bases: pyg4ometry.fluka.body.BodyMixin

Right Elliptical Cylinder

#### Parameters

- **name** (*str*) – of body
- **vertex** (*list*) – position [x, y, z] of one of the faces of the cylinder.
- **semiminor** (*list*) – vector [x, y, z] denoting the direction along the semiminor axis of the ellipse.
- **semimajor** (*list*) – vector [x, y, z] denoting the direction along the semimajor axis of the ellipse.

**\_withLengthSafety** (*safety, reg*)

**centre** (*aabb=None*)

**flukaFreeString** ()

**geant4Solid** (*reg, aabb=None*)

**rotation** ()

**class** pyg4ometry.fluka.body.**TRC** (*name, major\_centre, direction, major\_radius, minor\_radius, transform=None, flukaregistry=None, comment=""*)

Bases: pyg4ometry.fluka.body.BodyMixin

Truncated Right-angled Cone

#### Parameters

- **name** (*str*) – of body
- **major\_centre** (*list*) – vector [x, y, z] position of the centre of the larger face.
- **direction** (*list*) – vector [x, y, z] pointing from the larger face to the smaller face.
- **major\_radius** (*float*) – radius of the larger face.
- **minor\_radius** (*float*) – radius of the smaller face.

**\_withLengthSafety** (*safety, reg*)

**centre** (*aabb=None*)

**flukaFreeString** ()

**geant4Solid** (*registry, aabb=None*)

**rotation** ()

**class** pyg4ometry.fluka.body.**ELL** (*name, focus1, focus2, length, transform=None, flukaregistry=None, comment=""*)

Bases: pyg4ometry.fluka.body.BodyMixin

Ellipsoid of Revolution

#### Parameters

- **name** (*str*) – of body
- **focus1** (*list*) – position [x, y, z] denoting of one of the foci.
- **focus2** (*list*) – position [x, y, z] denoting the other focus.
- **length** (*float*) – length of the ellipse axis which the foci lie on.

**\_linearEccentricity** ()

**\_semiminor** ()

**\_withLengthSafety** (*safety, reg*)

**centre** (*aabb=None*)

**flukaFreeString** ()

**geant4Solid** (*greg, aabb=None*)

**rotation** ()

**class** pyg4ometry.fluka.body.**WED** (*name, vertex, edge1, edge2, edge3, transform=None, flukaregistry=None, comment=""*)

Bases: pyg4ometry.fluka.body.\_WED\_RAW

Right Angle Wedge

#### Parameters

- **name** (*str*) – of body
- **vertex** (*list*) – position [x, y, z] of one of the the rectangular corners.
- **edge1** (*list*) – vector [x, y, z] denoting height of the wedge.
- **edge2** (*list*) – vector [x, y, z] denoting width of the wedge.
- **edge3** (*list*) – vector [x, y, z] denoting length of the wedge.

**class** pyg4ometry.fluka.body.**RAW** (*name, vertex, edge1, edge2, edge3, transform=None, flukaregistry=None, comment=""*)

Bases: pyg4ometry.fluka.body.\_WED\_RAW

Right Angle Wedge

#### Parameters

- **name** (*str*) – of body
- **vertex** (*list*) – position [x, y, z] of one of the the rectangular corners.
- **edge1** (*list*) – vector [x, y, z] denoting height of the wedge.
- **edge2** (*list*) – vector [x, y, z] denoting width of the wedge.
- **edge3** (*list*) – vector [x, y, z] denoting length of the wedge.

```
class pyg4ometry.fluka.body.ARB(name, vertices, facenumbers, transform=None, flukaregistry=None, comment="")
```

Bases: `pyg4ometry.fluka.body.BodyMixin`

Arbitrary Convex Polyhedron

#### Parameters

- **name** (*str*) – of body
- **vertices** (*list*) – Eight vertices which make up the polyhedron as [[x1, y1, z1], [x2, y2, z2], ...]. There must be eight even if only six or seven vertices are needed to make up the polyhedron.
- **facenumbers** (*float*) – The faces of the polyhedron expressed as floats where each digit of the float refers to one of the vertices which makes up that face. Six must always be provided as [1234,8765, ...], even if only four or five faces are needed. Any unneeded faces must be set to 0 (no less than 4 sides). Note that the references to the vertices are not zero-counting. The order of the vertices denoted in the facenumbers must be either all clockwise or all anticlockwise, which if not obeyed will result in erroneous output without warning.

`_extent()`

`_faceNumbersToZeroCountingIndices()`

`_getVerticesAndPolygons()`

`_toTesselatedSolid(verticesAndPolygons, greg, addRegistry)`

`_toVerticesAndPolygons(reverse)`

`_withLengthSafety(safety, reg)`

`centre(aabb=None)`

`flukaFreeString()`

`geant4Solid(greg, aabb=None)`

`rotation()`

```
class pyg4ometry.fluka.body.XYP(name, z, transform=None, flukaregistry=None, comment="")
```

Bases: `pyg4ometry.fluka.body._HalfSpaceMixin`

Infinite half-space delimited by the x-y plane (perpendicular to the z-axis)

#### Parameters

- **name** (*str*) – of body
- **z** (*float*) – position of the x-y plane on the z-axis. All points less than z are considered to be part of this body.

`_withLengthSafety(safety, reg)`

`flukaFreeString()`

`toPlane()`



```
class pyg4ometry.fluka.body.XZP(name, y, transform=None, flukaregistry=None, comment="")
```

Bases: pyg4ometry.fluka.body.\_HalfSpaceMixin

Infinite half-space delimited by the x-y plane (perpendicular to the y-axis)

#### Parameters

- **name** (*str*) – of body
- **y** (*float*) – position of the x-y plane on the y-axis. All points less than y are considered to be part of this body.

```
_withLengthSafety(safety, reg)
```

```
flukaFreeString()
```

```
toPlane()
```

```
class pyg4ometry.fluka.body.YZP(name, x, transform=None, flukaregistry=None, comment="")
```

Bases: pyg4ometry.fluka.body.\_HalfSpaceMixin

Infinite half-space delimited by the x-y plane (perpendicular to the x-axis)

#### Parameters

- **name** (*str*) – of body
- **x** (*float*) – position of the x-y plane on the x-axis. All points less than x are considered to be part of this body.

```
_withLengthSafety(safety, reg)
```

```
flukaFreeString()
```

```
toPlane()
```

```
class pyg4ometry.fluka.body.PLA(name, normal, point, transform=None, flukaregistry=None, comment="")
```

Bases: pyg4ometry.fluka.body.\_HalfSpaceMixin

Infinite half-space delimited by the x-y plane (perpendicular to the z-axis) Generic infinite half-space.

#### Parameters

- **name** (*str*) – of body
- **normal** (*list*) – position of a point on the plane
- **normal** – vector perpendicular to the face of the plane, pointing away from the contents of the half space.

```
_withLengthSafety(safety, reg=None)
```

```
flukaFreeString()
```

```
rotation()
```

```
toPlane()
```

```
class pyg4ometry.fluka.body.XCC(name, y, z, radius, transform=None, flukaregistry=None, comment="")
```

Bases: pyg4ometry.fluka.body.\_InfiniteCylinderMixin, pyg4ometry.fluka.body.\_ShiftableCylinderMixin

Infinite Circular Cylinder parallel to the x-axis

#### Parameters

- **name** (*str*) – of body
- **y** (*float*) – position of the centre on the
- **z** (*float*) – position of the centre on the

- **radius** (*float*) – position of the centre on the

**\_withLengthSafety** (*safety, reg=None*)

**centre** (*aabb=None*)

**direction** ()

**flukaFreeString** ()

**point** ()

**rotation** ()

```
class pyg4ometry.fluka.body.YCC (name, z, x, radius, transform=None, flukaregistry=None,
                                comment="")
    Bases: pyg4ometry.fluka.body._InfiniteCylinderMixin, pyg4ometry.fluka.
            body._ShiftableCylinderMixin
```

Infinite Circular Cylinder parallel to the y-axis

#### Parameters

- **name** (*str*) – of body
- **z** (*float*) – position of the centre on the
- **x** (*float*) – position of the centre on the
- **radius** (*float*) – position of the centre on the

**\_withLengthSafety** (*safety, reg=None*)

**centre** (*aabb=None*)

**direction** ()

**flukaFreeString** ()

**point** ()

**rotation** ()

```
class pyg4ometry.fluka.body.ZCC (name, x, y, radius, transform=None, flukaregistry=None,
                                comment="")
    Bases: pyg4ometry.fluka.body._InfiniteCylinderMixin, pyg4ometry.fluka.
            body._ShiftableCylinderMixin
```

Infinite Circular Cylinder parallel to the z-axis

#### Parameters

- **name** (*str*) – of body
- **x** (*float*) – position of the centre on the
- **y** (*float*) – position of the centre on the
- **radius** (*float*) – position of the centre on the

**\_withLengthSafety** (*safety, reg=None*)

**centre** (*aabb=None*)

**direction** ()

**flukaFreeString** ()

**point** ()

**rotation** ()

```
class pyg4ometry.fluka.body.XEC(name, y, z, ysemi, zsemi, transform=None, flukareg-
                                istry=None, comment="")
Bases: pyg4ometry.fluka.body.BodyMixin, pyg4ometry.fluka.body.
       _ShiftableCylinderMixin
```

Infinite Elliptical Cylinder parallel to the x-axis

#### Parameters

- **name** (*str*) – of body
- **y** (*float*) – position of the centre on the
- **z** (*float*) – position of the centre on the
- **ysemi** (*float*) – position of the centre on the
- **zsemi** (*float*) – position of the centre on the

**\_withLengthSafety** (*safety*, *reg=None*)

**centre** (*aabb=None*)

**flukaFreeString**()

**geant4Solid** (*reg*, *aabb=None*)

**rotation**()

```
class pyg4ometry.fluka.body.YEC(name, z, x, zsemi, xsemi, transform=None, flukareg-
                                istry=None, comment="")
Bases: pyg4ometry.fluka.body.BodyMixin, pyg4ometry.fluka.body.
       _ShiftableCylinderMixin
```

Infinite Elliptical Cylinder parallel to the y-axis

#### Parameters

- **name** (*str*) – of body
- **z** (*float*) – position of the centre on the
- **x** (*float*) – position of the centre on the
- **zsemi** (*float*) – position of the centre on the
- **xsemi** (*float*) – position of the centre on the

**\_withLengthSafety** (*safety*, *reg=None*)

**centre** (*aabb=None*)

**flukaFreeString**()

**geant4Solid** (*reg*, *aabb=None*)

**rotation**()

```
class pyg4ometry.fluka.body.ZEC(name, x, y, xsemi, ysemi, transform=None, flukareg-
                                istry=None, comment="")
Bases: pyg4ometry.fluka.body.BodyMixin, pyg4ometry.fluka.body.
       _ShiftableCylinderMixin
```

Infinite Elliptical Cylinder parallel to the z-axis

#### Parameters

- **name** (*str*) – of body
- **x** (*float*) – position of the centre on the
- **y** (*float*) – position of the centre on the
- **xsemi** (*float*) – position of the centre on the

- **ysemi** (*float*) – position of the centre on the

**\_withLengthSafety** (*safety, reg=None*)

**centre** (*aabb=None*)

**flukaFreeString** ()

**geant4Solid** (*reg, aabb=None*)

**rotation** ()

**class** pyg4ometry.fluka.body.**QUA** (*name, cxx, cyy, czz, cxy, cxz, cyz, cx, cy, cz, c, transform=None, flukaregistry=None, comment="", \*\*kwargs*)

Bases: pyg4ometry.fluka.body.BodyMixin

Generic quadric

#### Parameters

- **name** (*str*) – of body
- **cxx** (*float*) –  $x^2$  coefficient
- **cyy** (*float*) –  $y^2$  coefficient
- **czz** (*float*) –  $z^2$  coefficient
- **cxy** (*float*) –  $xy$  coefficient
- **cxz** (*float*) –  $xz$  coefficient
- **cyz** (*float*) –  $yz$  coefficient
- **cx** (*float*) –  $x$  coefficient
- **cy** (*float*) –  $y$  coefficient
- **cz** (*float*) –  $z$  coefficient
- **c** (*constant*) – constant

**static** **\_quadricMatrixToCoefficients** (*matrix*)

**\_withLengthSafety** (*safety, reg=None*)

**centre** (*aabb=None*)

**coefficientsMatrix** ()

**flukaFreeString** ()

**geant4Solid** (*reg, aabb=None*)

**mesh** (*lower, upper, capping=True*)

**rotation** ()

## 8.9 Fluka module

Object to store geometry for FLUKA input and output. All of the FLUKA classes can be used without storing them in the Registry. The registry is used to write the FLUKA output file.

Class to read a FLUKA file.

## 8.10 Transformation

pyg4ometry.transformation.**are\_anti\_parallel** (*vector\_1, vector\_2, tolerance=1e-10*)

Check if vector *vector\_1* is parallel to vector *vector\_2* down to some tolerance.

`pyg4ometry.transformation.are_parallel (vector_1, vector_2, tolerance=1e-10)`

Check if vector `vector_1` is parallel to vector `vector_2` down to some tolerance.

`pyg4ometry.transformation.axisangle2matrix (axis, angle)`

`pyg4ometry.transformation.axisangle2tbxyz (axis, angle)`

`pyg4ometry.transformation.deg2rad (deg)`

`pyg4ometry.transformation.grad2rad (gradians)`

`pyg4ometry.transformation.matrix2axisangle (matrix)`

`pyg4ometry.transformation.matrix2tbxyz (matrix)`

Convert rotation matrix to Tait-Bryan angles. Order of rotation is x -> y -> z.

**Parameters** `matrix` – active (positive angle = anti-clockwise rotation about that axis when looking at the axis) matrix.

returns: [x, y, z] Tait-Bryan angles in a list.

`pyg4ometry.transformation.matrix_from (v_from, v_to)`

Returns the rotation matrix that rotates `v_from` to parallel to `v_to`.

Useful for ensuring a given face points in a certain direction.

`v_from` and `v_to` should be array-like three-vectors.

`pyg4ometry.transformation.rad2deg (rad)`

`pyg4ometry.transformation.reverse (angles)`

Invert the rotation represented by these angles.

`pyg4ometry.transformation.tbxyz2axisangle (rv)`

Tait-Bryan x-y-z rotation to axis-angle representation Algorithm from <http://www.sedris.org/wg8home/Documents/WG80485.pdf>

For converting rotation angles to an active axis/angle pair for use in pycsg. Order of rotation: x->y->z.

`pyg4ometry.transformation.tbxyz2matrix (angles)`

Convert tait bryan angles to a single passive rotation matrix. rotation order = x -> y -> z.

**Parameters** `angles` – list of angles: x, y, z

returns: rotation matrix

`pyg4ometry.transformation.tbzyx2matrix (angles)`

Convert tait bryan angles to a single passive rotation matrix. rotation order = x -> y -> z.

**Parameters** `angles` – list of angles: x, y, z

returns: rotation matrix

`pyg4ometry.transformation.two_fold_orientation (v1, v2, e1, e2)`

`matrix_from` will align one vector with another, but there are an infinite number of such matrices that align two vectors. This further constrains the rotation by introducing a second pair of vectors.

v1 start v v2 end v e1 start e e2 end v



## 9.1 Unit tests

```
cd pyg4ometry/pyg4ometry/test
python2.7 runTests.py
```

## 9.2 Coverage

```
cd pyg4ometry/coverage
./runCoverage.sh
```

## 9.3 Profiling

```
python2.7 -m cProfile -s tottime myscript.py > myscript.log
```

```
pycallgraph-2.7 graphviz -- ../pyg4ometry/test/python/T008_Sphere.py
```

## 9.4 Updating A Version

Update the version number in the following files:

- *setup.py*
- *setup.cfg*
- *pyg4ometry/docs/source/conf.py*

Make manual and commit to *pyg4ometry/docs/pyg4ometry.pdf*.

## 9.5 Updating Copyright

Update the year in the following files:

- *LICENCE.txt*
- *README.md*
- *docs/source/conf.py*
- *docs/source/licence.rst*





## VERSION HISTORY

### 10.1 v 1.0.0 - 2021 / 07 / 01

- Working version regularly used, submitted to CPC Journal for review.
- Based on CGAL for Boolean mesh operations, using pybind11, whereas previously was based on pycgal.
- FLUKA conversion to pyg4ometry and GDML has been reimplemented from the pyfluka package.
- Extensive code testing has been introduced and basic functionality documented.
- Given the strictness of CGAL, many bugs in meshing algorithms were fixed for all solids in *pyg4ometry.geant4.solid*.

### 10.2 Pre-History

- v0.2.0 - 2018 / 06 / 23
- v0.1.4 - 2018 / 06 / 04
- v0.1.2 - 2018 / 06 / 03
- v0.1.1 - 2018 / 06 / 03
- v0.1.0 - 2017 / 06 / 05
- v0.4.0 - 2017 / 10 / 17
- v0.3.0 - 2017 / 07 / 06



## INDICES AND TABLES

- `genindex`
- `modindex`
- `search`



## PYTHON MODULE INDEX

### p

pyg4ometry.fluka.body, 64  
pyg4ometry.fluka.FlukaRegistry, 72  
pyg4ometry.fluka.Reader, 72  
pyg4ometry.freecad.Reader, 60  
pyg4ometry.gdml.Defines, 41  
pyg4ometry.gdml.Reader, 61  
pyg4ometry.gdml.Writer, 63  
pyg4ometry.geant4.LogicalVolume, 54  
pyg4ometry.geant4.ParameterisedVolume, 56  
pyg4ometry.geant4.PhysicalVolume, 55  
pyg4ometry.geant4.ReplicaVolume, 56  
pyg4ometry.geant4.solid.Box, 42  
pyg4ometry.geant4.solid.Cons, 43  
pyg4ometry.geant4.solid.CutTubs, 42  
pyg4ometry.geant4.solid.Ellipsoid, 47  
pyg4ometry.geant4.solid.EllipticalTube, 47  
pyg4ometry.geant4.solid.ExtrudedSolid, 49  
pyg4ometry.geant4.solid.GenericPolycone, 46  
pyg4ometry.geant4.solid.GenericTrap, 51  
pyg4ometry.geant4.solid.Hype, 48  
pyg4ometry.geant4.solid.Intersection, 53  
pyg4ometry.geant4.solid.Orb, 44  
pyg4ometry.geant4.solid.Para, 43  
pyg4ometry.geant4.solid.Paraboloid, 48  
pyg4ometry.geant4.solid.Plane, 41  
pyg4ometry.geant4.solid.Polycone, 45  
pyg4ometry.geant4.solid.Polyhedra, 46  
pyg4ometry.geant4.solid.Sphere, 44  
pyg4ometry.geant4.solid.Subtraction, 53  
pyg4ometry.geant4.solid.TessellatedSolid, 52  
pyg4ometry.geant4.solid.Tet, 48  
pyg4ometry.geant4.solid.Torus, 45  
pyg4ometry.geant4.solid.Trap, 44  
pyg4ometry.geant4.solid.Trd, 43  
pyg4ometry.geant4.solid.Tubs, 42  
pyg4ometry.geant4.solid.TwistedBox, 49  
pyg4ometry.geant4.solid.TwistedTrap, 49  
pyg4ometry.geant4.solid.TwistedTrd, 50  
pyg4ometry.geant4.solid.TwistedTubs, 51  
pyg4ometry.geant4.solid.Union, 52  
pyg4ometry.geant4.solid.Wedge, 41  
pyg4ometry.stl.Reader, 61  
pyg4ometry.transformation, 72  
pyg4ometry.visualisation.VtkViewer, 58



## Symbols

<code>__add__()</code>	<code>(pyg4ometry.gdml.Defines.ScalarBase method), 37</code>	<code>(pyg4ometry.fluka.body.ELL method), 67</code>
<code>__add__()</code>	<code>(pyg4ometry.gdml.Defines.VectorBase method), 39</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.PLA method), 69</code>
<code>__mul__()</code>	<code>(pyg4ometry.gdml.Defines.ScalarBase method), 37</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.QUA method), 72</code>
<code>__mul__()</code>	<code>(pyg4ometry.gdml.Defines.VectorBase method), 39</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.RCC method), 66</code>
<code>__neg__()</code>	<code>(pyg4ometry.gdml.Defines.ScalarBase method), 37</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.REC method), 66</code>
<code>__rmul__()</code>	<code>(pyg4ometry.gdml.Defines.VectorBase method), 39</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.RPP method), 65</code>
<code>__rsub__()</code>	<code>(pyg4ometry.gdml.Defines.ScalarBase method), 37</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.SPH method), 66</code>
<code>__sub__()</code>	<code>(pyg4ometry.gdml.Defines.ScalarBase method), 37</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.TRC method), 67</code>
<code>__sub__()</code>	<code>(pyg4ometry.gdml.Defines.VectorBase method), 40</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.XCC method), 70</code>
<code>_extent()</code>	<code>(pyg4ometry.fluka.body.ARB method), 68</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.XEC method), 71</code>
<code>_faceNumbersToZeroCountingIndices()</code>	<code>(pyg4ometry.fluka.body.ARB method), 68</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.XYP method), 68</code>
<code>_getVerticesAndPolygons()</code>	<code>(pyg4ometry.fluka.body.ARB method), 68</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.XZP method), 69</code>
<code>_linearEccentricity()</code>	<code>(pyg4ometry.fluka.body.ELL method), 67</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.YCC method), 70</code>
<code>_quadricMatrixToCoefficients()</code>	<code>(pyg4ometry.fluka.body.QUA static method), 72</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.YEC method), 71</code>
<code>_semiminor()</code>	<code>(pyg4ometry.fluka.body.ELL method), 67</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.YZP method), 69</code>
<code>_toTesselatedSolid()</code>	<code>(pyg4ometry.fluka.body.ARB method), 68</code>	<code>_withLengthSafety() (pyg4ometry.fluka.body.ZCC method), 69</code>
<code>_toVerticesAndPolygons()</code>	<code>(pyg4ometry.fluka.body.ARB method), 68</code>	
<code>_withLengthSafety()</code>	<code>(pyg4ometry.fluka.body.ARB method), 68</code>	
<code>_withLengthSafety()</code>	<code>(pyg4ometry.fluka.body.BOX method), 65</code>	
<code>_withLengthSafety()</code>		

70  
 \_withLengthSafety() (pyg4ometry.fluka.body.ZEC method), 72

**A**

acos() (in module pyg4ometry.gdml.Defines), 39  
 add() (pyg4ometry.geant4.LogicalVolume.LogicalVolume method), 55  
 add\_element\_massfraction() (pyg4ometry.geant4.Material method), 54  
 add\_element\_natoms() (pyg4ometry.geant4.Material method), 54  
 add\_material() (pyg4ometry.geant4.Material method), 54  
 add\_property() (pyg4ometry.geant4.Material method), 54  
 addAuxiliaryInfo() (pyg4ometry.geant4.LogicalVolume.LogicalVolume method), 55  
 addAxes() (pyg4ometry.visualisation.VtkViewer.VtkViewer method), 58  
 addAxesWidget() (pyg4ometry.visualisation.VtkViewer.VtkViewer method), 58  
 addBDSIMObject() (pyg4ometry.geant4.LogicalVolume.LogicalVolume method), 55  
 addBooleanSolidRecursive() (pyg4ometry.visualisation.VtkViewer.VtkViewer method), 58  
 addCutterPlane() (pyg4ometry.visualisation.VtkViewer.VtkViewer method), 58  
 addDefine() (pyg4ometry.geant4.Registry method), 53  
 addDetector() (pyg4ometry.gdml.Writer.Writer method), 63  
 addLogicalVolume() (pyg4ometry.geant4.Registry method), 53  
 addLogicalVolume() (pyg4ometry.visualisation.VtkViewer.VtkViewer method), 58  
 addLogicalVolumeBounding() (pyg4ometry.visualisation.VtkViewer.VtkViewer method), 58  
 addLogicalVolumeRecursive() (pyg4ometry.visualisation.VtkViewer.VtkViewer method), 58  
 addMaterial() (pyg4ometry.geant4.Registry method), 53  
 addMaterialVisOption() (pyg4ometry.visualisation.VtkViewer.VtkViewer method), 58  
 addMesh() (pyg4ometry.visualisation.VtkViewer.VtkViewer method), 58  
 addMeshSimple() (pyg4ometry.visualisation.VtkViewer.VtkViewer method), 59  
 addPhysicalVolume() (pyg4ometry.geant4.Registry method), 53  
 addSolid() (pyg4ometry.geant4.Registry method), 53  
 AnalyseGeometryComplexity() (in module pyg4ometry.geant4), 54  
 ARB (class in pyg4ometry.fluka.body), 68  
 are\_anti\_parallel() (in module pyg4ometry.transformation), 72  
 are\_parallel() (in module pyg4ometry.transformation), 72  
 asin() (in module pyg4ometry.gdml.Defines), 39  
 assemblyVolume() (pyg4ometry.geant4.LogicalVolume.LogicalVolume method), 55  
 atan() (in module pyg4ometry.gdml.Defines), 39  
 axesFromExtents() (in module pyg4ometry.visualisation.VtkViewer), 60  
 axisangle2matrix() (in module pyg4ometry.transformation), 73  
 axisangle2tbxyz() (in module pyg4ometry.transformation), 73

**B**

BOX (class in pyg4ometry.fluka.body), 65  
 Box (class in pyg4ometry.geant4.solid.Box), 42

**C**

centre() (pyg4ometry.fluka.body.ARB method), 68  
 centre() (pyg4ometry.fluka.body.BOX method), 65  
 centre() (pyg4ometry.fluka.body.ELL method), 67  
 centre() (pyg4ometry.fluka.body.QUA method), 72  
 centre() (pyg4ometry.fluka.body.RCC method), 66  
 centre() (pyg4ometry.fluka.body.REC method), 66  
 centre() (pyg4ometry.fluka.body.RPP method), 65  
 centre() (pyg4ometry.fluka.body.SPH method), 66  
 centre() (pyg4ometry.fluka.body.TRC method), 67  
 centre() (pyg4ometry.fluka.body.XCC method), 70  
 centre() (pyg4ometry.fluka.body.XEC method), 71  
 centre() (pyg4ometry.fluka.body.YCC method), 70  
 centre() (pyg4ometry.fluka.body.YEC method), 71  
 centre() (pyg4ometry.fluka.body.ZCC method), 70  
 centre() (pyg4ometry.fluka.body.ZEC method), 72  
 checkDefineName() (pyg4ometry.gdml.Writer.Writer method), 63  
 checkLogicalVolumeName() (pyg4ometry.gdml.Writer.Writer method), 63  
 checkMaterialName() (pyg4ometry.gdml.Writer.Writer method), 63  
 checkOverlaps() (pyg4ometry.geant4.LogicalVolume.LogicalVolume method), 55  
 checkPhysicalVolumeName() (pyg4ometry.gdml.Writer.Writer method), 63  
 checkSolidName() (pyg4ometry.gdml.Writer.Writer method), 63



clipSolid() (pyg4ometry.geant4.LogicalVolume.LogicalVolume  
method), 55

coefficientsMatrix() (pyg4ometry.fluka.body.QUA  
method), 72

Cons (class in pyg4ometry.geant4.solid.Cons), 43

Constant (class in pyg4ometry.gdml.Defines), 37

convertFlat() (pyg4ometry.freecad.Reader.Reader  
method), 61

convertStructure() (pyg4ometry.freecad.Reader.Reader  
method), 61

cos() (in module pyg4ometry.gdml.Defines), 39

createParameterisedMeshes() (pyg4ometry.geant4.ParameterisedVolume.ParameterisedVolume  
method), 57

createPosition() (pyg4ometry.gdml.Writer.Writer  
method), 63

createQuadrangularFacet() (pyg4ometry.gdml.Writer.Writer  
method), 63

createReplicaMeshes() (pyg4ometry.geant4.ReplicaVolume.ReplicaVolume  
method), 56

createrzPoint() (pyg4ometry.gdml.Writer.Writer  
method), 63

createSection() (pyg4ometry.gdml.Writer.Writer  
method), 63

createTessellatedSolid() (in module  
pyg4ometry.geant4.solid.TessellatedSolid),  
52

createTriangularFacet() (pyg4ometry.gdml.Writer.Writer  
method), 63

createTwoDimVertex() (pyg4ometry.gdml.Writer.Writer  
method), 63

createzPlane() (pyg4ometry.gdml.Writer.Writer  
method), 63

cullDaughtersOutsideSolid() (pyg4ometry.geant4.LogicalVolume.LogicalVolume  
method), 55

CutTubs (class in pyg4ometry.geant4.solid.CutTubs),  
42

**D**

deg2rad() (in module pyg4ometry.transformation),  
73

direction() (pyg4ometry.fluka.body.XCC method),  
70

direction() (pyg4ometry.fluka.body.YCC method),  
70

direction() (pyg4ometry.fluka.body.ZCC method),  
70

**E**

ELL (class in pyg4ometry.fluka.body), 67

Ellipsoid (class in pyg4ometry.geant4.solid.Ellipsoid), 47

EllipticalTube (class in pyg4ometry.geant4.solid.EllipticalTube),  
47

eval() (pyg4ometry.gdml.Defines.Constant method),  
37

eval() (pyg4ometry.gdml.Defines.Expression  
method), 38

eval() (pyg4ometry.gdml.Defines.Quantity method),  
38

eval() (pyg4ometry.gdml.Defines.Variable method),  
38

eval() (pyg4ometry.gdml.Defines.VectorBase  
method), 40

eval() (pyg4ometry.gdml.Matrix method), 41

exp() (in module pyg4ometry.gdml.Defines), 39

exportCutterSection() (pyg4ometry.visualisation.VtkViewer.VtkViewer  
method), 59

exportGLTFScene() (pyg4ometry.visualisation.VtkViewer.VtkViewer  
method), 59

exportOBJScene() (pyg4ometry.visualisation.VtkViewer.VtkViewer  
method), 59

exportScreenShot() (pyg4ometry.visualisation.VtkViewer.VtkViewer  
method), 59

exportVRMLScene() (pyg4ometry.visualisation.VtkViewer.VtkViewer  
method), 59

Expression (class in pyg4ometry.gdml.Defines), 38

extent() (pyg4ometry.geant4.LogicalVolume.LogicalVolume  
method), 55

extent() (pyg4ometry.geant4.ParameterisedVolume.ParameterisedVolume  
method), 57

extent() (pyg4ometry.geant4.PhysicalVolume.PhysicalVolume  
method), 56

extent() (pyg4ometry.geant4.ReplicaVolume.ReplicaVolume  
method), 56

extractStructureNodeData() (pyg4ometry.gdml.Reader.Reader  
method), 61

ExtrudedSolid (class in  
pyg4ometry.geant4.solid.ExtrudedSolid),  
49

**F**

FacetListAxisAlignedExtent() (in module  
pyg4ometry.freecad.Reader), 60

findLogicalByName() (pyg4ometry.geant4.LogicalVolume.LogicalVolume  
method), 55

flukaFreeString() (pyg4ometry.fluka.body.ARB  
method), 68

flukaFreeString() (pyg4ometry.fluka.body.BOX  
method), 65

flukaFreeString() (pyg4ometry.fluka.body.ELL  
method), 67

flukaFreeString() (pyg4ometry.fluka.body.PLA  
method), 69

flukaFreeString() (*pyg4ometry.fluka.body.QUA method*), 72  
 flukaFreeString() (*pyg4ometry.fluka.body.RCC method*), 66  
 flukaFreeString() (*pyg4ometry.fluka.body.REC method*), 66  
 flukaFreeString() (*pyg4ometry.fluka.body.RPP method*), 65  
 flukaFreeString() (*pyg4ometry.fluka.body.SPH method*), 66  
 flukaFreeString() (*pyg4ometry.fluka.body.TRC method*), 67  
 flukaFreeString() (*pyg4ometry.fluka.body.XCC method*), 70  
 flukaFreeString() (*pyg4ometry.fluka.body.XEC method*), 71  
 flukaFreeString() (*pyg4ometry.fluka.body.XYP method*), 68  
 flukaFreeString() (*pyg4ometry.fluka.body.XZP method*), 69  
 flukaFreeString() (*pyg4ometry.fluka.body.YCC method*), 70  
 flukaFreeString() (*pyg4ometry.fluka.body.YEC method*), 71  
 flukaFreeString() (*pyg4ometry.fluka.body.YZP method*), 69  
 flukaFreeString() (*pyg4ometry.fluka.body.ZCC method*), 70  
 flukaFreeString() (*pyg4ometry.fluka.body.ZEC method*), 72

## G

geant4Solid() (*pyg4ometry.fluka.body.ARB method*), 68  
 geant4Solid() (*pyg4ometry.fluka.body.BOX method*), 65  
 geant4Solid() (*pyg4ometry.fluka.body.ELL method*), 67  
 geant4Solid() (*pyg4ometry.fluka.body.QUA method*), 72  
 geant4Solid() (*pyg4ometry.fluka.body.RCC method*), 66  
 geant4Solid() (*pyg4ometry.fluka.body.REC method*), 66  
 geant4Solid() (*pyg4ometry.fluka.body.RPP method*), 65  
 geant4Solid() (*pyg4ometry.fluka.body.SPH method*), 66  
 geant4Solid() (*pyg4ometry.fluka.body.TRC method*), 67  
 geant4Solid() (*pyg4ometry.fluka.body.XEC method*), 71  
 geant4Solid() (*pyg4ometry.fluka.body.YEC method*), 71  
 geant4Solid() (*pyg4ometry.fluka.body.ZEC method*), 72  
 GenericPolycone (class in *pyg4ometry.geant4.solid.GenericPolycone*),

46

GenericTrap (class in *pyg4ometry.geant4.solid.GenericTrap*), 51  
 getMaterialVisOptions() (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 59  
 getOverlapVisOptions() (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 59  
 getPhysicalVolumes() (*pyg4ometry.geant4.ReplicaVolume.ReplicaVolume method*), 56  
 getRegistry() (*pyg4ometry.freecad.Reader.Reader method*), 61  
 getRegistry() (*pyg4ometry.gdml.Reader.Reader method*), 61  
 getRegistry() (*pyg4ometry.stl.Reader.Reader method*), 61  
 getSolid() (*pyg4ometry.stl.Reader.Reader method*), 61  
 getValueOrExpr() (*pyg4ometry.gdml.Writer.Writer method*), 63  
 getValueOrExprFromInstance() (*pyg4ometry.gdml.Writer.Writer method*), 63  
 grad2rad() (in module *pyg4ometry.transformation*), 73

## H

Hype (class in *pyg4ometry.geant4.solid.Hype*), 48

## I

Intersection (class in *pyg4ometry.geant4.solid.Intersection*), 53

## K

kPhi (*pyg4ometry.geant4.ReplicaVolume.ReplicaVolume.Axis attribute*), 56  
 kRho (*pyg4ometry.geant4.ReplicaVolume.ReplicaVolume.Axis attribute*), 56  
 kXAxis (*pyg4ometry.geant4.ReplicaVolume.ReplicaVolume.Axis attribute*), 56  
 kYAxis (*pyg4ometry.geant4.ReplicaVolume.ReplicaVolume.Axis attribute*), 56  
 kZAxis (*pyg4ometry.geant4.ReplicaVolume.ReplicaVolume.Axis attribute*), 56

## L

lengths() (*pyg4ometry.fluka.body.BOX method*), 65  
 lengths() (*pyg4ometry.fluka.body.RPP method*), 65  
 load() (*pyg4ometry.freecad.Reader.Reader method*), 61  
 load() (*pyg4ometry.gdml.Reader.Reader method*), 61  
 load() (*pyg4ometry.stl.Reader.Reader method*), 61

loadAuxiliaryData() (pyg4ometry.freecad.Reader.Reader method), 61

log() (in module pyg4ometry.gdml.Defines), 39

log10() (in module pyg4ometry.gdml.Defines), 39

LogicalVolume (class in pyg4ometry.geant4.LogicalVolume), 54

## M

makeLogicalPhysicalNameSets() (pyg4ometry.geant4.LogicalVolume.LogicalVolume method), 55

makeMaterialNameSet() (pyg4ometry.geant4.LogicalVolume.LogicalVolume method), 55

makeSolidTessellated() (pyg4ometry.geant4.LogicalVolume.LogicalVolume method), 55

makeWorldVolume() (pyg4ometry.geant4.LogicalVolume.LogicalVolume method), 55

Material (class in pyg4ometry.geant4), 54

Matrix (class in pyg4ometry.gdml), 40

matrix2axisangle() (in module pyg4ometry.transformation), 73

matrix2tboxyz() (in module pyg4ometry.transformation), 73

matrix\_from() (in module pyg4ometry.transformation), 73

mesh() (pyg4ometry.fluka.body.QUA method), 72

mesh() (pyg4ometry.geant4.solid.EllipticalTube.EllipticalTube method), 47

mesh() (pyg4ometry.geant4.solid.Sphere.Sphere method), 44

MeshAnalysis() (in module pyg4ometry.freecad.Reader), 60

MeshCleaning() (in module pyg4ometry.freecad.Reader), 60

MeshToFacetList() (in module pyg4ometry.freecad.Reader), 61

MouseInteractorNamePhysicalVolume (class in pyg4ometry.visualisation.VtkViewer), 58

## N

nonzero() (pyg4ometry.gdml.Defines.VectorBase method), 40

## O

Orb (class in pyg4ometry.geant4.solid.Orb), 44

## P

Para (class in pyg4ometry.geant4.solid.Para), 43

Paraboloid (class in pyg4ometry.geant4.solid.Paraboloid), 48

ParameterisedVolume (class in pyg4ometry.geant4.ParameterisedVolume), 56

ParameterisedVolume.BoxDimensions (class in pyg4ometry.geant4.ParameterisedVolume), 57

ParameterisedVolume.ConeDimensions (class in pyg4ometry.geant4.ParameterisedVolume), 57

ParameterisedVolume.EllipsoidDimensions (class in pyg4ometry.geant4.ParameterisedVolume), 57

ParameterisedVolume.HypeDimensions (class in pyg4ometry.geant4.ParameterisedVolume), 57

ParameterisedVolume.OrbDimensions (class in pyg4ometry.geant4.ParameterisedVolume), 57

ParameterisedVolume.ParaDimensions (class in pyg4ometry.geant4.ParameterisedVolume), 57

ParameterisedVolume.PolyconeDimensions (class in pyg4ometry.geant4.ParameterisedVolume), 57

ParameterisedVolume.PolyhedraDimensions (class in pyg4ometry.geant4.ParameterisedVolume), 57

ParameterisedVolume.SphereDimensions (class in pyg4ometry.geant4.ParameterisedVolume), 57

ParameterisedVolume.TorusDimensions (class in pyg4ometry.geant4.ParameterisedVolume), 57

ParameterisedVolume.TrapDimensions (class in pyg4ometry.geant4.ParameterisedVolume), 57

ParameterisedVolume.TrdDimensions (class in pyg4ometry.geant4.ParameterisedVolume), 57

ParameterisedVolume.TubeDimensions (class in pyg4ometry.geant4.ParameterisedVolume), 57

parseBox() (pyg4ometry.gdml.Reader.Reader method), 62

parseCone() (pyg4ometry.gdml.Reader.Reader method), 62

parseCutTube() (pyg4ometry.gdml.Reader.Reader method), 62

parseDefines() (pyg4ometry.gdml.Reader.Reader method), 62

parseEllipsoid() (pyg4ometry.gdml.Reader.Reader method), 62

parseEllipticalCone() (pyg4ometry.gdml.Reader.Reader method), 62

parseEllipticalTube() (pyg4ometry.gdml.Reader.Reader method), 62

parseExtrudedSolid() (pyg4ometry.gdml.Reader.Reader method), 62

62  
 parseGenericPolycone() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseGenericPolyhedra() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseGenericTrap() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseHype() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseIntersection() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseMaterials() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseMultiUnion() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseOpticalSurface() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseOrb() (pyg4ometry.gdml.Reader.Reader method), 62  
 parsePara() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseParaboloid() (pyg4ometry.gdml.Reader.Reader method), 62  
 parsePhysicalVolumeChildren() (pyg4ometry.gdml.Reader.Reader method), 62  
 parsePolycone() (pyg4ometry.gdml.Reader.Reader method), 62  
 parsePolyhedra() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseScaledSolid() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseSolidLoop() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseSolids() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseSphere() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseStructure() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseSubtraction() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseTessellatedSolid() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseTet() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseTorus() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseTrap() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseTrd() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseTube() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseTwistedBox() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseTwistedTrap() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseTwistedTrd() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseTwistedTubs() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseUnion() (pyg4ometry.gdml.Reader.Reader method), 62  
 parseUserInfo() (pyg4ometry.gdml.Reader.Reader method), 63  
 parseVector() (pyg4ometry.gdml.Reader.Reader method), 63  
 PartFeatureGlobalPlacement() (in module pyg4ometry.freecad.Reader), 61  
 PhysicalVolume (class in pyg4ometry.geant4.PhysicalVolume), 55  
 PLA (class in pyg4ometry.fluka.body), 69  
 Plane (class in pyg4ometry.geant4.solid.Plane), 41  
 point() (pyg4ometry.fluka.body.XCC method), 70  
 point() (pyg4ometry.fluka.body.YCC method), 70  
 point() (pyg4ometry.fluka.body.ZCC method), 70  
 Polycone (class in pyg4ometry.geant4.solid.Polycone), 45  
 Polyhedra (class in pyg4ometry.geant4.solid.Polyhedra), 46  
 Position (class in pyg4ometry.gdml), 40  
 printPartFeatures() (pyg4ometry.freecad.Reader.Reader method), 61  
 printStructure() (pyg4ometry.freecad.Reader.Reader method), 61  
 printViewParameters() (pyg4ometry.visualisation.VtkViewer.VtkViewer method), 59  
 PubViewer (in module pyg4ometry.visualisation.VtkViewer), 58  
 pyg4ometry.fluka.body (module), 64  
 pyg4ometry.fluka.FlukaRegistry (module), 72  
 pyg4ometry.fluka.Reader (module), 72  
 pyg4ometry.freecad.Reader (module), 60



pyg4ometry.gdml.Defines (*module*), 37, 39, 41  
 pyg4ometry.gdml.Reader (*module*), 61  
 pyg4ometry.gdml.Writer (*module*), 63  
 pyg4ometry.geant4.LogicalVolume (*module*), 54  
 pyg4ometry.geant4.ParameterisedVolume (*module*), 56  
 pyg4ometry.geant4.PhysicalVolume (*module*), 55  
 pyg4ometry.geant4.ReplicaVolume (*module*), 56  
 pyg4ometry.geant4.solid.Box (*module*), 42  
 pyg4ometry.geant4.solid.Cons (*module*), 43  
 pyg4ometry.geant4.solid.CutTubs (*module*), 42  
 pyg4ometry.geant4.solid.Ellipsoid (*module*), 47  
 pyg4ometry.geant4.solid.EllipticalTube (*module*), 47  
 pyg4ometry.geant4.solid.ExtrudedSolid (*module*), 49  
 pyg4ometry.geant4.solid.GenericPolycone (*module*), 46  
 pyg4ometry.geant4.solid.GenericTrap (*module*), 51  
 pyg4ometry.geant4.solid.Hype (*module*), 48  
 pyg4ometry.geant4.solid.Intersection (*module*), 53  
 pyg4ometry.geant4.solid.Orb (*module*), 44  
 pyg4ometry.geant4.solid.Para (*module*), 43  
 pyg4ometry.geant4.solid.Paraboloid (*module*), 48  
 pyg4ometry.geant4.solid.Plane (*module*), 41  
 pyg4ometry.geant4.solid.Polycone (*module*), 45  
 pyg4ometry.geant4.solid.Polyhedra (*module*), 46  
 pyg4ometry.geant4.solid.Sphere (*module*), 44  
 pyg4ometry.geant4.solid.Subtraction (*module*), 53  
 pyg4ometry.geant4.solid.TessellatedSolid (*module*), 52  
 pyg4ometry.geant4.solid.Tet (*module*), 48  
 pyg4ometry.geant4.solid.Torus (*module*), 45  
 pyg4ometry.geant4.solid.Trap (*module*), 44  
 pyg4ometry.geant4.solid.Trd (*module*), 43  
 pyg4ometry.geant4.solid.Tubs (*module*), 42  
 pyg4ometry.geant4.solid.TwistedBox (*module*), 49  
 pyg4ometry.geant4.solid.TwistedTrap (*module*), 49  
 pyg4ometry.geant4.solid.TwistedTrd (*module*), 50  
 pyg4ometry.geant4.solid.TwistedTubs (*module*), 51

pyg4ometry.geant4.solid.Union (*module*), 52  
 pyg4ometry.geant4.solid.Wedge (*module*), 41  
 pyg4ometry.stl.Reader (*module*), 61  
 pyg4ometry.transformation (*module*), 72  
 pyg4ometry.visualisation.VtkViewer (*module*), 58

## Q

QUA (*class in pyg4ometry.fluka.body*), 72  
 Quantity (*class in pyg4ometry.gdml.Defines*), 38

## R

rad2deg () (*in module pyg4ometry.transformation*), 73  
 RAW (*class in pyg4ometry.fluka.body*), 67  
 RCC (*class in pyg4ometry.fluka.body*), 66  
 Reader (*class in pyg4ometry.freecad.Reader*), 61  
 Reader (*class in pyg4ometry.gdml.Reader*), 61  
 Reader (*class in pyg4ometry.stl.Reader*), 61  
 REC (*class in pyg4ometry.fluka.body*), 66  
 recurseObjectTree () (*pyg4ometry.freecad.Reader.Reader method*), 61  
 recursePrintObjectTree () (*pyg4ometry.freecad.Reader.Reader method*), 61  
 Registry (*class in pyg4ometry.geant4*), 53  
 relabelModel () (*pyg4ometry.freecad.Reader.Reader method*), 61  
 ReplicaVolume (*class in pyg4ometry.geant4.ReplicaVolume*), 56  
 ReplicaVolume.Axis (*class in pyg4ometry.geant4.ReplicaVolume*), 56  
 reverse () (*in module pyg4ometry.transformation*), 73  
 rightButtonPressEvent () (*pyg4ometry.visualisation.VtkViewer.MouseInteractorNamePhy method*), 58  
 Rotation (*class in pyg4ometry.gdml*), 40  
 rotation () (*pyg4ometry.fluka.body.ARB method*), 68  
 rotation () (*pyg4ometry.fluka.body.BOX method*), 65  
 rotation () (*pyg4ometry.fluka.body.ELL method*), 67  
 rotation () (*pyg4ometry.fluka.body.PLA method*), 69  
 rotation () (*pyg4ometry.fluka.body.QUA method*), 72  
 rotation () (*pyg4ometry.fluka.body.RCC method*), 66  
 rotation () (*pyg4ometry.fluka.body.REC method*), 66  
 rotation () (*pyg4ometry.fluka.body.RPP method*), 65

- `rotation()` (*pyg4ometry.fluka.body.SPH method*), 66
  - `rotation()` (*pyg4ometry.fluka.body.TRC method*), 67
  - `rotation()` (*pyg4ometry.fluka.body.XCC method*), 70
  - `rotation()` (*pyg4ometry.fluka.body.XEC method*), 71
  - `rotation()` (*pyg4ometry.fluka.body.YCC method*), 70
  - `rotation()` (*pyg4ometry.fluka.body.YEC method*), 71
  - `rotation()` (*pyg4ometry.fluka.body.ZCC method*), 70
  - `rotation()` (*pyg4ometry.fluka.body.ZEC method*), 72
  - RPP (*class in pyg4ometry.fluka.body*), 64
- ## S
- ScalarBase (*class in pyg4ometry.gdml.Defines*), 37
  - Scale (*class in pyg4ometry.gdml*), 40
  - `set_pressure()` (*pyg4ometry.geant4.Material method*), 54
  - `set_temperature()` (*pyg4ometry.geant4.Material method*), 54
  - `setCameraFocusPosition()` (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 59
  - `setCutterNormal()` (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 59
  - `setCutterOrigin()` (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 59
  - `setExpression()` (*pyg4ometry.gdml.Defines.ScalarBase method*), 37
  - `setLogicalVolumeMaterial()` (*pyg4ometry.freecad.Reader.Reader method*), 61
  - `setMaterialVisOptions()` (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 59
  - `setName()` (*pyg4ometry.gdml.Defines.ScalarBase method*), 37
  - `setName()` (*pyg4ometry.gdml.Defines.VectorBase method*), 40
  - `setOpacity()` (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 59
  - `setOpacityOverlap()` (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 59
  - `setRandomColours()` (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 60
  - `setRegistry()` (*pyg4ometry.gdml.Defines.ScalarBase method*), 37
  - `setRegistry()` (*pyg4ometry.gdml.Defines.VectorBase method*), 40
  - `setSolid()` (*pyg4ometry.geant4.LogicalVolume.LogicalVolume method*), 55
  - `setSurface()` (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 60
  - `setSurfaceOverlap()` (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 60
  - `setWireframe()` (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 60
  - `setWireframeOverlap()` (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 60
  - `simplifyModel()` (*pyg4ometry.freecad.Reader.Reader method*), 61
  - `sin()` (*in module pyg4ometry.gdml.Defines*), 39
  - SPH (*class in pyg4ometry.fluka.body*), 65
  - Sphere (*class in pyg4ometry.geant4.solid.Sphere*), 44
  - `sqrt()` (*in module pyg4ometry.gdml.Defines*), 39
  - `start()` (*pyg4ometry.visualisation.VtkViewer.VtkViewer method*), 60
  - `state_variables` (*pyg4ometry.geant4.Material attribute*), 54
  - Subtraction (*class in pyg4ometry.geant4.solid.Subtraction*), 53
- ## T
- `tan()` (*in module pyg4ometry.gdml.Defines*), 39
  - `tbxyz2axisangle()` (*in module pyg4ometry.transformation*), 73
  - `tbxyz2matrix()` (*in module pyg4ometry.transformation*), 73
  - `tbzyx2matrix()` (*in module pyg4ometry.transformation*), 73
  - TessellatedSolid (*class in pyg4ometry.geant4.solid.TessellatedSolid*), 52
  - Tet (*class in pyg4ometry.geant4.solid.Tet*), 48
  - `toPlane()` (*pyg4ometry.fluka.body.PLA method*), 69
  - `toPlane()` (*pyg4ometry.fluka.body.XYP method*), 68
  - `toPlane()` (*pyg4ometry.fluka.body.XZP method*), 69
  - `toPlane()` (*pyg4ometry.fluka.body.YZP method*), 69
  - Torus (*class in pyg4ometry.geant4.solid.Torus*), 45
  - Trap (*class in pyg4ometry.geant4.solid.Trap*), 44
  - TRC (*class in pyg4ometry.fluka.body*), 66
  - Trd (*class in pyg4ometry.geant4.solid.Trd*), 43
  - TVoid (*class in pyg4ometry.geant4.solid.Tubs*), 42
  - TwistedBox (*class in pyg4ometry.geant4.solid.TwistedBox*), 49
  - TwistedTrap (*class in pyg4ometry.geant4.solid.TwistedTrap*), 49
  - TwistedTrd (*class in pyg4ometry.geant4.solid.TwistedTrd*), 50
  - TwistedTubs (*class in pyg4ometry.geant4.solid.TwistedTubs*), 51

`two_fold_orientation()` (in module `pyg4ometry.transformation`), 73

## U

`Union` (class in `pyg4ometry.geant4.solid.Union`), 52

`upgradeToStringExpression()` (in module `pyg4ometry.gdml.Defines`), 37

`upgradeToTransformation()` (in module `pyg4ometry.gdml.Defines`), 41

`upgradeToVector()` (in module `pyg4ometry.gdml.Defines`), 41

## V

`Variable` (class in `pyg4ometry.gdml.Defines`), 38

`VectorBase` (class in `pyg4ometry.gdml.Defines`), 39

`view()` (`pyg4ometry.visualisation.VtkViewer.VtkViewer` method), 60

`viewSection()` (`pyg4ometry.visualisation.VtkViewer.VtkViewer` method), 60

`visualise()` (`pyg4ometry.stl.Reader.Reader` method), 61

`VtkViewer` (class in `pyg4ometry.visualisation.VtkViewer`), 58

`VtkViewerColoured` (class in `pyg4ometry.visualisation.VtkViewer`), 60

`VtkViewerColouredMaterial` (class in `pyg4ometry.visualisation.VtkViewer`), 60

## W

`WED` (class in `pyg4ometry.fluka.body`), 67

`Wedge` (class in `pyg4ometry.geant4.solid.Wedge`), 41

`write()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeAssemblyVolume()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeAuxiliary()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeBorderSurface()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeBox()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeCons()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeCutTubs()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeDefaultGDML()` (`pyg4ometry.stl.Reader.Reader` method), 61

`writeDefaultLattice()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeDefine()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeDivisionVolume()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeEllipsoid()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeEllipticalCone()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeEllipticalTube()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeExtrudedSolid()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeGenericPolycone()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeGenericPolyhedra()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeGenericTrap()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeGmadTester()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeGMADTesterNoBeamline()` (`pyg4ometry.gdml.Writer.Writer` method), 63

`writeHype()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeIntersection()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeLogicalVolume()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeMaterial()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeMultiUnion()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeOpticalSurface()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeOrb()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writePara()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeParaboloid()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeParametrisedVolume()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writePhysicalVolume()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writePolycone()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writePolyhedra()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`Writer` (class in `pyg4ometry.gdml.Writer`), 63

`writeReplicaVolume()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeScaled()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeSkinSurface()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`WriteSMeshFile()` (in module `pyg4ometry.freecad.Reader`), 61

`writeSolid()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeSphere()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeSubtraction()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeTessellatedSolid()` (`pyg4ometry.gdml.Writer.Writer` method), 64

`writeTet()` (`pyg4ometry.gdml.Writer.Writer` method), 64

*method*), 64  
writeTorus() (pyg4ometry.gdml.Writer.Writer  
*method*), 64  
writeTrap() (pyg4ometry.gdml.Writer.Writer  
*method*), 64  
writeTrd() (pyg4ometry.gdml.Writer.Writer  
*method*), 64  
writeTubs() (pyg4ometry.gdml.Writer.Writer  
*method*), 64  
writeTwistedBox()  
(pyg4ometry.gdml.Writer.Writer *method*), 64  
writeTwistedTrap()  
(pyg4ometry.gdml.Writer.Writer *method*), 64  
writeTwistedTrd()  
(pyg4ometry.gdml.Writer.Writer *method*), 64  
writeTwistedTubs()  
(pyg4ometry.gdml.Writer.Writer *method*), 64  
writeUnion() (pyg4ometry.gdml.Writer.Writer  
*method*), 64  
writeVectorVariable()  
(pyg4ometry.gdml.Writer.Writer *method*), 64

## X

XCC (class in pyg4ometry.fluka.body), 69  
XEC (class in pyg4ometry.fluka.body), 70  
XYP (class in pyg4ometry.fluka.body), 68  
XZP (class in pyg4ometry.fluka.body), 68

## Y

YCC (class in pyg4ometry.fluka.body), 70  
YEC (class in pyg4ometry.fluka.body), 71  
YZP (class in pyg4ometry.fluka.body), 69

## Z

ZCC (class in pyg4ometry.fluka.body), 70  
ZEC (class in pyg4ometry.fluka.body), 71